



# ForceField Manual

*Amsterdam Modeling Suite 2022.1*

**[www.scm.com](http://www.scm.com)**

**Feb 23, 2022**



# CONTENTS

<b>1</b>	<b>Introduction</b>	<b>1</b>
1.1	Available force fields . . . . .	1
1.2	ForceField-GUI . . . . .	1
1.3	What's new in ForceField 2021 . . . . .	1
1.4	What's new in ForceField 2020 . . . . .	2
1.4.1	New features . . . . .	2
1.5	Force field setup for AMS applications . . . . .	2
1.6	Classical force fields . . . . .	2
<b>2</b>	<b>Atom typing behavior</b>	<b>3</b>
2.1	UFF . . . . .	3
2.2	Other forcefields . . . . .	3
<b>3</b>	<b>Input via the AMS system block</b>	<b>5</b>
3.1	ForceField input example . . . . .	5
3.2	Antechamber integration . . . . .	7
<b>4</b>	<b>ForceField Engine Options</b>	<b>9</b>
4.1	Common options . . . . .	9
4.1.1	Type . . . . .	9
4.1.2	Non-bonded screening . . . . .	9
4.1.3	Feedback . . . . .	10
4.1.4	Bonds usage . . . . .	10
4.1.5	Ewald summation . . . . .	11
4.1.6	Disabling energy terms . . . . .	12
4.1.7	Guessing or loading partial charges . . . . .	13
	GuessCharges . . . . .	13
	LoadCharges . . . . .	14
4.2	Amber force field options . . . . .	14
4.3	UFF options . . . . .	15
4.4	APPLE&P force field options . . . . .	16
<b>5</b>	<b>Examples</b>	<b>19</b>
5.1	Example: single point for aspirin with UFF . . . . .	19
5.2	Example: partial charges and total charge . . . . .	20
5.3	Example: load partial charges from another engine . . . . .	30
5.4	Example: load atom types from a previous run . . . . .	32
5.5	Example: using amber or tripos . . . . .	35
5.6	Example: calculate some simple properties for water . . . . .	36
5.7	Example: single point for ammonia with TRIPPOS . . . . .	37

<b>6 Required citations</b>	<b>39</b>
6.1 External programs and libraries . . . . .	39
<b>7 Parameter files</b>	<b>41</b>
7.1 UFF parameters . . . . .	41
7.1.1 User-modified force fields (expert option) . . . . .	41
7.2 AMBER parameters . . . . .	44
7.2.1 AMBER forcefield file . . . . .	44
7.2.2 SCM forcefield file . . . . .	45
<b>8 Potential shapes</b>	<b>55</b>
<b>9 Periodic ForceField</b>	<b>57</b>
<b>10 References</b>	<b>59</b>
<b>11 Keywords</b>	<b>61</b>
11.1 Links to manual entries . . . . .	61
11.2 Summary of all keywords . . . . .	61
<b>Index</b>	<b>69</b>

## INTRODUCTION

As per 2020 UFF force fields and simple classical force fields are unified in the ForceField engine. This replaces the old UFF engine and the NewMM functionality from ADF.

### 1.1 Available force fields

The default force field is UFF, it requires no configuration. UFF (Universal Force Field) is a full periodic table force field that can be used to calculate single point energies, do geometry optimizations, calculate frequencies, etc. It is also the default pre-optimizer in the Graphical User interface (GUI) to clean up manually drawn structures. For details on the inner workings of the force field, see the 1992 paper by Rappe et al. [[1](#) (page 59)]. By default UFF uses non-zero charges for water molecules only.

Other available force fields managed by this engine include Amber95, Tripos 5.2, GAFF and APPLE&P [[9](#) (page 59)].

### 1.2 ForceField-GUI

Note that the graphical user interface UFF-GUI enables all users to set up force field calculations with a few mouse clicks. Most force fields require atom typing, and this needs to be done by hand. When using UFF, also for pre-optimizing, it is important to remember that any force field method relies on a set of parameters. This means that even though UFF supports all elements up to Z=103, it might not generate the desired structures for uncommon oxidation states in metallic structures. If this is the case, you could add new parameters to UFF or attach dummy hydrogen atoms to the metal atom.

### 1.3 What's new in ForceField 2021

- The engine has been parallelized with MPI using force decomposition.
- The particle mesh Ewald method (implemented through the helPME library (<https://github.com/andysim/helpme>)) is now used for electrostatic interactions in 3D systems.
- The default non-bonded cutoff has been reduced to 15 Angstrom, a value more typical in the force-field community.
- The engine has been optimized to be on par with the industry standards. The total speed-up compared to version 2020 can be up to factor 500.

## 1.4 What's new in ForceField 2020

### 1.4.1 New features

- Periodic support (chains,slabs, and crystals) for all force field types
- Import force field parameters from amber “.dat” files

**shell script without atom typing:**

```
#!/bin/sh

# This is a shell script for the ForceField engine

# You should use '$AMSBIN/ams' instead.

$AMSBIN/ams <<eor
    # Input options for the AMS driver:

        Task GeometryOptimization

        System
            Atoms
                H 0.0 0.0 0.0
                H 0.9 0.0 0.0
            End
        End

    # The input options for the ForceField, which are described in this manual,
    # should be specified in the 'Engine ForceField' block:

    Engine ForceField
        # the default one is UFF, requiring no options
    EndEngine
eor
```

## 1.5 Force field setup for AMS applications

When you do a geometry optimization or perform a MD calculation the details of the force field are determined only once and kept constant during the run. This applies to bond orders, partial charges, etc. In case of a polarizable force field (not currently supported) the charges are of course allowed to change.

## 1.6 Classical force fields

Most force fields require atom typing, as well as atomic charge specifications, see [Examples](#) (page 19).

## ATOM TYPING BEHAVIOR

To use a classical forcefield each atom should be given a type, and a partial charge. The power of the UFF forcefield is that this atomtyping is done automatically. For other force fields the atomtyping for most systems still has to be done by hand, possibly with the help of an external program. Unlike UFF parameters, the available parameters for the other available force fields typically cover only a fraction of all chemical elements. Nonetheless, experimental atomtyping options are available for small organic molecules (GAFF), and for biological systems (AMBER).

### 2.1 UFF

Atom typing is the process of matching MM atom types to elements. For example, a Carbon atom becomes a C\_1, C\_2, C\_3 or C\_R, depending on the number (and type) of bonds it has to neighboring atoms. UFF is capable of finding a matching MM atom type on its own, but might not always succeed in doing so. When doing calculations with UFF, it is important to check the beginning of the output file, as the program will print the detected MM atom types there. You can also take matters into your own hands, and tell UFF what MM atom types you want it to use (see the section on Input and examples).

The atom typing in UFF is mostly controlled by the elements and mmatomtypes parameter files, however, some part of it is hidden in the code itself and is (at the moment) not accessible to users. This is done by UFF to differentiate between:

- Carbon: double-bonded sp<sup>2</sup> carbon (C\_2) vs aromatic carbon (C\_R), if any of the orders are close to 2, it's C\_2.
- Oxygen: having a bond to silicon gives O\_3\_z; otherwise, having bond order of 1.44 or higher gives O\_R, provided that the partner is not a hydrogen. Otherwise, it's just an O\_3.
- Sulfur: having a bond order greater than 1.3 gives aromatic S\_R.

By default, zero charges are used, unless a water molecule is detected.

### 2.2 Other forcefields

Automatic atomtyping via an experimental integration of the Antechamber toolkit is available for the Generalized AMBER Force Field (GAFF) for small organic molecules. This option was introduced in the 2020 release of AMS, and is still considered experimental and disabled by default.

See also:

*Antechamber integration for GAFF forcefields* (page 7)

Some atomtyping functionality for biological systems can be accessed via the GUI, using pdb files as input. A pdb file can be loaded into amsinput and then under the regions the residues can be found. Still, charges need to be set by hand.

Custom force field parameters can be provided as forcefield files. The two supported formats are “.ff” (originating from the ADF and QUILD programs) and the much more widely used amber “.dat” files.

## INPUT VIA THE AMS SYSTEM BLOCK

While usually options for an AMS engine are defined in its engine block, for the ForceField engine three ingredients are defined via the AMS system block: bonds, atom types and (partial) charges.

Here are some logical options

- 1) Specify Everything: elements, coordinates, MM atom types, charges, and bonds
- 2) Specify elements, coordinates, and bonds (UFF only)
- 3) Specify elements and coordinates (UFF only, most convenient)

Currently, for most force fields, everything needs to be specified (option 1). UFF and GAFF allow the automatic determination of bonds and atom types (option 2 and 3). For GAFF this option is considered experimental as of the 2020 release and is disabled by default, see [Antechamber integration](#) (page 7) below. See also the [BondsUsage](#) (page 10) key on how bond information can be tweaked.

### 3.1 ForceField input example

#### 1) Specify Elements, coordinates, MM Atom Types, Charges, and bonds:

```
$AMSBIN/ams << eor

Task GeometryOptimization

System
  Atoms
    C  1.36012328  -0.14520095  0.60144543  ForceField.Type=C_3
    ↵ForceField.Charge=0.000000
    C  0.00000000  0.00000000  0.00000000  ForceField.Type=C_2
    ↵ForceField.Charge=0.000000
    H  2.09833847  -0.46327872  -0.16560721  ForceField.Type=H_
    ↵ForceField.Charge=0.000000
    H  1.32657807  -0.90546800  1.40917410  ForceField.Type=H_
    ↵ForceField.Charge=0.000000
    H  1.67935140  0.82750664  1.02977296  ForceField.Type=H_
    ↵ForceField.Charge=0.000000
    H  -0.83486863  0.30434056  0.62258487  ForceField.Type=H_
    ↵ForceField.Charge=0.000000
    O  -0.18030374  -0.22462371  -1.18585739  ForceField.Type=O_2
    ↵ForceField.Charge=0.000000
  End
  BondOrders
    1 5 1.0
```

(continues on next page)

(continued from previous page)

```

1 4 1.0
1 3 1.0
1 2 1.0
2 6 1.0
2 7 2.0
End
End

Engine ForceField
EndEngine

eor

```

The format in the bonds section is: atom A, atom B, bond order.

## 2) Specify Elements, coordinates, and bonds (UFF only):

If we leave out the MM atom types and charges, UFF will determine the MM atom types automatically from the bond information:

```

$AMSBIN/ams << eor

Task GeometryOptimization

System
Atoms
    C  1.36012328 -0.14520095  0.60144543
    C  0.00000000  0.00000000  0.00000000
    H  2.09833847 -0.46327872 -0.16560721
    H  1.32657807 -0.90546800  1.40917410
    H  1.67935140  0.82750664  1.02977296
    H -0.83486863  0.30434056  0.62258487
    O -0.18030374 -0.22462371 -1.18585739
End
BondOrders
    1 5 1.0
    1 4 1.0
    1 3 1.0
    1 2 1.0
    2 6 1.0
    2 7 2.0
End
End

Engine ForceField
EndEngine

eor

```

## 3) Specify Elements and coordinates (UFF only):

The third input format is similar to the second, but without a Bonds section in System:

```

$AMSBIN/ams << eor

Task GeometryOptimization

System

```

(continues on next page)

(continued from previous page)

```

Atoms
C 1.36012328 -0.14520095 0.60144543
C 0.00000000 0.00000000 0.00000000
H 2.09833847 -0.46327872 -0.16560721
H 1.32657807 -0.90546800 1.40917410
H 1.67935140 0.82750664 1.02977296
H -0.83486863 0.30434056 0.62258487
O -0.18030374 -0.22462371 -1.18585739
End
End

Engine ForceField
EndEngine

eor

```

The GUI generates inputs of the second or third type, depending on the “Use existing bonds” setting in the ForceField main tab. Note that to specify the MM Atom Types, the charges also need to be set. UFF has automatic bond guessing and a very simple automatic charge guessing only assigning charges to atoms of water molecules.

## 3.2 Antechamber integration

For the GAFF force field there is an experimental integration of the [Antechamber toolkit](http://ambermd.org/antechamber/antechamber.html) (<http://ambermd.org/antechamber/antechamber.html>) for automatic atom typing. This allows the GAFF force field to be used with option 2 (only bonds and coordinates specified) and option 3 (coordinates only). As of the 2020 release of AMS, this option is still considered experimental and disabled by default. It can be enabled and configured from the input:

AntechamberIntegration Yes/No
-------------------------------

### **AntechamberIntegration**

**Type** Bool

**Default value** No

**GUI name** Automatic atom typing

**Description** EXPERIMENTAL: Use the Antechamber program to automatically determine atom types for the GAFF force field. This may run a geometry optimization with MOPAC under the hood in order to determine the charges (see keyword AntechamberTask), which might not work for very large systems.

AntechamberTask [GeometryOptimization   SinglePoint]
--

### **AntechamberTask**

**Type** Multiple Choice

**Default value** GeometryOptimization

**Options** [GeometryOptimization, SinglePoint]

**Description** If antechamber is envoked to guess atomtypes and charges (GAFF force field), select the task for charge guessing with MOPAC



---

CHAPTER  
FOUR

---

## FORCEFIELD ENGINE OPTIONS

Details of the ForceField engine can be set via its input block. Some option are specific to UFF and others to other force fields.

### 4.1 Common options

These options apply to any force field.

#### 4.1.1 Type

There are a few predefined force field types, that, if used, require no other input.

```
Type [UFF | Amber95 | GAFF | Tripos5.2 | APPLE&P | UserDefined]
```

**Type**

**Type** Multiple Choice

**Default value** UFF

**Options** [UFF, Amber95, GAFF, Tripos5.2, APPLE&P, UserDefined]

**Description** Type of force field to be used

#### 4.1.2 Non-bonded screening

The long range interaction (dispersion and Coulomb) are the most expensive to evaluate. This gives you the option to screen the interaction more aggressively.

```
NonBondedCutoff float
```

**NonBondedCutoff**

**Type** Float

**Default value** 15.0

**Unit** Angstrom

**Description** Distance beyond which the non-bonded pair interactions (Coulomb and Van der Waals) will be ignored.

The interactions are smoothly damped starting from 0.9\*NonBondedCutoff.

Has no effect on the Coulomb term for periodic systems, as Ewald summation is used.

It is usually a good idea to add some “skin” to the cutoff above when it’s used for computing a neighbor list for changing geometries (e.g. during molecular dynamics or geometry optimization). This way, the neighbor list will not need to be re-computed when atoms move a little. This may save some time because generating a neighbor list can be quite costly. The following option sets the thickness of the “skin”:

```
NeighborListSkin float
```

**NeighborListSkin**

**Type** Float

**Default value** 2.5

**Unit** Angstrom

**Description** Thickness of the buffer region added to the NonBondedCutoff when building a neighbor list.

---

**Note:** This option also affects the cutoff used when generating a neighbor list in the real-space part of the Ewald summation but then it is added to the cutoff radius is used there.

---

### 4.1.3 Feedback

If you want to know more about the details of the force field you should crank up the verbosity.

```
Verbosity [Silent | Normal | Verbose | VeryVerbose]
```

**Verbosity**

**Type** Multiple Choice

**Default value** Silent

**Options** [Silent, Normal, Verbose, VeryVerbose]

**Description** Controls the verbosity of the engine.

### 4.1.4 Bonds usage

Bonds can be specified in the input, still you may not want to use those. Here are some options to control this.

```
BondsUsage [Input | None | Guess | Auto]
```

**BondsUsage**

**Type** Multiple Choice

**Default value** Auto

**Options** [Input, None, Guess, Auto]

**Description** Controls what bonds are used by the engine. The choice auto means: guess in case there are no bonds. Guessing only happens at the first MD step, or first geometry optimization step.

### 4.1.5 Ewald summation

For periodic systems the Ewald summation is performed for the Coulomb interaction. It has a couple of options:

```
EwaldSummation
  Alpha float
  Enabled Yes/No
  GridSpacing float
  RealSpaceCutoff float
  Tolerance float
End
```

#### **EwaldSummation**

**Type** Block

**Description** Configures the details of the particle mesh Ewald (PME) summation of the Coulomb interaction.

#### **Alpha**

**Type** Float

**Default value** -1.0

**Unit** 1/Angstrom

**Description** This parameter shifts the workload from real space (smaller alpha) to reciprocal space (larger alpha). Using a larger [Alpha] without decreasing [GridSpacing] may increase the error in the reciprocal-space contribution. Set to zero to disable the reciprocal-space Ewald part. Negative value means the [Alpha] will be determined automatically from the [Tolerance] and [RealSpaceCutoff] values.

#### **Enabled**

**Type** Bool

**Default value** Yes

**Description** Set to false to use real-space pair summation instead of the Ewald, which is the default and the only option for molecules, 1D and 2D periodic systems.

#### **GridSpacing**

**Type** Float

**Default value** 0.5

**Unit** Angstrom

**Description** Grid spacing in the particle mesh Ewald method. Smaller grid spacing will make the reciprocal energy calculation more accurate but slower. Using a larger [Alpha] value may require a smaller GridSpacing to be accurate.

#### **RealSpaceCutoff**

**Type** Float

**Default value** 0.0

**Unit** Angstrom

**Description** Set the cutoff value for the real-space summation. Zero means the internal defaults will be used depending on the [Alpha] (if Alpha=0 then the cutoff will be set to 50 Bohr, otherwise to 20 Bohr).

#### Tolerance

**Type** Float

**Default value** 1e-10

**Description** Value of the error function that should be used to determine the cutoff radius for real-space Ewald summation if [Alpha] is set on input. Alternatively, if the [RealSpaceCut-off] is set but [Alpha] is not then the [Tolerance] value affects the [Alpha]. Larger values will make the real-space summation faster but less accurate.

### 4.1.6 Disabling energy terms

By default all force field energy terms are calculated, however, you can disable each one of them individually.

```
EnergyTerms
Angle Yes/No
Coulomb Yes/No
Dispersion Yes/No
Inversion Yes/No
Stretch Yes/No
Torsion Yes/No
End
```

#### EnergyTerms

**Type** Block

**Description** expert key, that allows you to disable specific energy terms.

##### Angle

**Type** Bool

**Default value** Yes

**Description** Whether to use angle (bend) energy.

##### Coulomb

**Type** Bool

**Default value** Yes

**Description** Whether to use coulomb energy.

##### Dispersion

**Type** Bool

**Default value** Yes

**Description** Whether to use dispersion energy.

##### Inversion

**Type** Bool

**Default value** Yes

**Description** Whether to use inversion energy.

##### Stretch

**Type** Bool

**Default value** Yes

**Description** Whether to use stretch energy.

#### Torsion

**Type** Bool

**Default value** Yes

**Description** Whether to use torsion energy.

### 4.1.7 Guessing or loading partial charges

The UFF forcefield has some very rudimentary partial charges guessing, only setting charges for atoms in water molecules. By default the partial charges in a force field calculation are zero. Essentially you will always need to specify atomic charges to make the results more realistic, either via the input or using one or the following options.

See also example [LoadCharges](#) (page 30), and [ChargedMolecules](#) (page 20).

#### GuessCharges

The simplest way is the use the GuessCharges key, that uses an engine that can calculate atomic charges. By default DFTB is used. DFTB is of course much more expensive than a forcefield, but if you run a MD calculation you can maybe afford a single DFTB calculation on the system.

```
GuessCharges Yes/No
```

#### GuessCharges

**Type** Bool

**Default value** No

**Description** Use another engine to calculate/guess the charges to be used by the force field.

If you want to control the engine use the GuessChargesConfig key.

```
GuessChargesConfig
  EngineType string
End
```

#### GuessChargesConfig

**Type** Block

**Description** Guess charges to be used by the forcefield

#### EngineType

**Type** String

**Default value** dftb

**Description** Engine that can calculate or guess charges

## LoadCharges

You have more control over the charge guessing, by loading the charges of another calculation. This way you can set any engine specific detail, such as the basis set, or functional.

You can load charges from a previous calculation to be used as force field charges.

```
LoadCharges
  File string
  Section string
  Variable string
End
```

### LoadCharges

**Type** Block

**Description** Load charges from a file to be used as forcefield charges

#### File

**Type** String

**Description** Name of the (kf) file

#### Section

**Type** String

**Default value** AMSResults

**Description** Section name of the kf file

#### Variable

**Type** String

**Default value** Charges

**Description** variable name of the kf file

## 4.2 Amber force field options

These options are relevant for the Amber and GAFF force fields:

```
AllowMissingParameters Yes/No
```

### AllowMissingParameters

**Type** Bool

**Default value** No

**Description** When parameters are not found for bonds, angles, dihedrals, or inversions, the first entry in the database will be used.

```
CheckDuplicateRules Yes/No
```

### CheckDuplicateRules

**Type** Bool

**Default value** Yes

**Description** The database could contain duplicate entries. For torsions this is a feature, and the potentials will be added. For all other terms this is not allowed, and if detected the program stops. One should fix the database or set the checking to false. As always the last entry will be used.

```
ForceFieldFile string
```

#### ForceFieldFile

**Type** String

**Default value**

**GUI name** Force field library

**Description** Path to the force field parameter file

## 4.3 UFF options

The following options are only relevant for the UFF force field:

```
UFF
  AtomTypesFile string
  Database string
  ElementsFile string
  Library [UFF | UFF4MOF | UFF4MOF-II]
End
```

#### UFF

**Type** Block

**Description** Option for the UFF force field.

#### AtomTypesFile

**Type** String

**Default value** mmatomtypes\_db

**Description** Expert option: Select the file that defines how UFF determines the atom types

#### Database

**Type** String

**Default value** general\_db

**Description** Expert option: Select the file that defines the UFF parameters per atom type

#### ElementsFile

**Type** String

**Default value** elements\_db

**Description** Expert option: Select the file that defines the elements known to UFF

#### Library

**Type** Multiple Choice

**Default value** UFF

**Options** [UFF, UFF4MOF, UFF4MOF-II]

**GUI name** Force field library

**Description** Selects the used parameter library.

## 4.4 APPLE&P force field options

The *ForceFieldFile* (page 15) key is mandatory and it should contain path to the APPLE&P forcefield file. This file is usually tailored for each system specifically.

Additionally, the following options are relevant for the APPLE&P force field.

```
DipoleConvergenceThreshold float
```

**DipoleConvergenceThreshold**

**Type** Float

**Default value** 1e-06

**Unit** a.u.

**Description** Convergence criterion for induced point dipoles, in atomic units. When the length of every atomic delta\_mu vector between two iterations becomes below the tolerance, the procedure is considered converged.

The repulsion/dispersion and Coulomb interaction between atoms connected by a bond or by a valence angle are excluded in APPLE&P. Those between atoms connected by a dihedral (the so called 1-4 neighbors) may be scaled down and the scaling factors can be changed using the following options:

```
APPLE&P
  LongRangeCorrection Yes/No
  MuMu14Scaling float
  QMu14Scaling float
  QQ14Scaling float
  RD14Scaling float
End
```

**APPLE&P**

**Type** Block

**Description** Options for the APPLE&P force field.

**LongRangeCorrection**

**Type** Bool

**Default value** Yes

**GUI name** Add long-range correction

**Description** Add a long-range dispersion correction to the energy and pressure for 3D-periodic systems.

This correction should be enabled only for a homogeneous liquid.

**MuMu14Scaling**

**Type** Float

**Default value** 1.0

**GUI name** Mu-Mu 3rd-neighbor scaling

**Description** Scaling factor for dipole-dipole interactions between atoms connected to 3rd order (via a dihedral).

#### **QM14Scaling**

**Type** Float

**Default value** 0.8

**GUI name** Q-Mu 3rd-neighbor scaling

**Description** Scaling factor for charge-dipole interactions between atoms connected to 3rd order (via a dihedral).

#### **QQ14Scaling**

**Type** Float

**Default value** 0.8

**GUI name** Q-Q 3rd-neighbor scaling

**Description** Scaling factor for charge-charge interactions between atoms connected to 3rd order (via a dihedral).

#### **RD14Scaling**

**Type** Float

**Default value** 1.0

**GUI name** RD 3rd-neighbor scaling

**Description** Scaling factor for repulsion/dispersion interactions between atoms connected to 3rd order (via a dihedral).



## EXAMPLES

The `$AMSHOME/examples/forcefield` directory contains many different example files, covering various aspects. This is a selection of relevant examples showing what the engine input looks like.

We do not repeat here all functionality that is available from the AMS driver level, see the [AMS Examples](#).

### 5.1 Example: single point for aspirin with UFF

Download `SP_aspirin.run`

```
#!/bin/sh

$AMSBIN/ams << eor

Task SinglePoint

Properties Gradients=yes

System
Atoms
    C      0.000000  0.000000  0.000000
    C      1.402231  0.000000  0.000000
    C      2.091015  1.220378  0.000000
    C      1.373539  2.425321  0.004387
    C     -0.034554  2.451759  0.016301
    C     -0.711248  1.213529  0.005497
    O     -0.709522  3.637718  0.019949
    C     -2.141910  1.166077 -0.004384
    O     -2.727881  2.161939 -0.690916
    C     -0.730162  4.530447  1.037168
    C     -0.066705  4.031914  2.307663
    H     -0.531323 -0.967191 -0.007490
    H      1.959047 -0.952181 -0.004252
    H      3.194073  1.231720 -0.005862
    H      1.933090  3.376356 -0.002746
    O     -2.795018  0.309504  0.548870
    H     -2.174822  2.832497 -1.125018
    O     -1.263773  5.613383  0.944221
    H     -0.337334  4.693941  3.161150
    H      1.041646  4.053111  2.214199
    H     -0.405932  3.005321  2.572927
End
End
```

(continues on next page)

(continued from previous page)

```
Engine ForceField
EndEngine

eor
```

## 5.2 Example: partial charges and total charge

This example shows you some ways to use partial atomic charges for ions. The atomic charges should add up to the total charge.

Download ChargedMolecules.run

```
#!/bin/sh

# Here we consider a Butane molecule with the C in the end groups changed to N
# The ion has a charge of plus two.
# The (partial) atomic charges used in the forcefield need to add up to the total
# charge

# There is explicit specification via the input, Loading charges, and guessing charges

# Charges taken "manually" from a DFTB calc., specified via the System%Atoms block

export AMS_JOBNAME=C2H10N2++

rm -rf $AMS_JOBNAME.results

"$AMSBIN/ams" << eor

Task GeometryOptimization

Properties Charges=yes

GeometryOptimization
  Convergence Gradients=1.0e-6
End

System
  Atoms
    N -0.005073166519502884 0.008770355996886468    1.060120635725228    ForceField.
    ↵Charge=-0.224106970135964811E+000
      C -0.003379615065181385 0.005774705419397744 -0.4323726711546611 ↵
    ↵ForceField.Charge=0.481803346892513140E-001
      C 0.7147029862216027 -1.238161594687982 -0.9787933548287219 ↵
    ↵ForceField.Charge=0.481357488383262755E-001
      N 0.7166487936613554 -1.241183181538415 -2.471469363728673 ↵
    ↵ForceField.Charge=-0.224111043229265006E+000
      H -0.489254727061788 0.8470579056083724 1.393322418122902 ↵
    ↵ForceField.Charge=0.327048167700910608E+000
      H 0.9419603270459358 0.02859511576851682 1.443864570589139 ↵
    ↵ForceField.Charge=0.312019677649949589E+000
```

(continues on next page)

(continued from previous page)

H -0.4954439060007188	-0.801643243084588	1.443905390218997	↳
↳ForceField.Charge=0.312016700963803795E+000			
H 0.497012567535054	0.9247340386709353	-0.7538297483507286	↳
↳ForceField.Charge=0.112420754799849087E+000			
H -1.049427360359161	0.0320094307806696	-0.7537906795101232	↳
↳ForceField.Charge=0.112425859786873958E+000			
H 1.760678843023289	-1.264262738726653	-0.6572703272452628	↳
↳ForceField.Charge=0.112415997624231642E+000			
H 0.2140471968077103	-2.156981931600252	-0.6574882069415752	↳
↳ForceField.Charge=0.112419970108937881E+000			
H 1.207324110469442	-0.4308282262683778	-2.854859298860555	↳
↳ForceField.Charge=0.312043881750391661E+000			
H -0.2304034502578771	-1.260970512043685	-2.855040966499596	↳
↳ForceField.Charge=0.312048243703216099E+000			
H 1.200917269444972	-2.079821003490794	-2.803581935602674	↳
↳ForceField.Charge=0.327042675749500744E+000			
End			
GuessBonds True			
Charge 2.0			
End			
Engine ForceField			
EndEngine			
eor			
# Now the neutral molecule, to show it behaves differently			
export AMS_JOBNAME=C2H10N2			
rm -rf \$AMS_JOBNAME.results			
"\$AMSBIN/ams" << eor			
Task GeometryOptimization			
Properties Charges=yes			
GeometryOptimization			
Convergence Gradients=1.0e-6			
End			
System			
Atoms			
N -0.005073166519502884	0.008770355996886468	1.060120635725228	ForceField.
↳Charge=-0.571011278205044492E+000			
C -0.003379615065181385	0.005774705419397744	-0.4323726711546611	↳
↳ForceField.Charge=-0.628203646719944775E-001			
C 0.7147029862216027	-1.238161594687982	-0.9787933548287219	↳
↳ForceField.Charge=-0.628837746183146251E-001			
N 0.7166487936613554	-1.241183181538415	-2.471469363728673	↳
↳ForceField.Charge=-0.571125568500377101E+000			
H -0.489254727061788	0.8470579056083724	1.393322418122902	↳
↳ForceField.Charge=0.194366247283714433E+000			

(continues on next page)

(continued from previous page)

H 0.9419603270459358 0.02859511576851682	1.443864570589139	✉
↪ForceField.Charge=0.194416030458134853E+000		
H -0.4954439060007188 -0.801643243084588	1.443905390218997	✉
↪ForceField.Charge=0.194415295916033237E+000		
H 0.497012567535054 0.9247340386709353	-0.7538297483507286	✉
↪ForceField.Charge=0.253223131130085044E-001		
H -1.049427360359161 0.0320094307806696	-0.7537906795101232	✉
↪ForceField.Charge=0.253801306729796901E-001		
H 1.760678843023289 -1.264262738726653	-0.6572703272452628	✉
↪ForceField.Charge=0.253595653793994673E-001		
H 0.2140471968077103 -2.156981931600252	-0.6574882069415752	✉
↪ForceField.Charge=0.254060553518517668E-001		
H 1.207324110469442 -0.4308282262683778	-2.854859298860555	✉
↪ForceField.Charge=0.194371032691725371E+000		
H -0.2304034502578771 -1.260970512043685	-2.855040966499596	✉
↪ForceField.Charge=0.194368207022870332E+000		
H 1.200917269444972 -2.079821003490794	-2.803581935602674	✉
↪ForceField.Charge=0.194436108106012751E+000		
End		
GuessBonds True		
End		
Engine ForceField		
EndEngine		
eor		
# The remaining calculations are again on the +2 ion		
# Charges obtained with GuessCharges, using by default dftb.		
export AMS_JOBNAME=C2H10N2++.guessed		
rm -rf \$AMS_JOBNAME.results		
"\$AMSBIN/ams" << eor		
Task GeometryOptimization		
Properties Charges=yes		
GeometryOptimization		
Convergence Gradients=1.0e-6		
End		
System		
Atoms		
N -0.005073166519502884 0.008770355996886468 1.060120635725228		
C -0.003379615065181385 0.005774705419397744 -0.4323726711546611		
C 0.7147029862216027 -1.238161594687982 -0.9787933548287219		
N 0.7166487936613554 -1.241183181538415 -2.471469363728673		
H -0.489254727061788 0.8470579056083724 1.393322418122902		
H 0.9419603270459358 0.02859511576851682 1.443864570589139		
H -0.4954439060007188 -0.801643243084588 1.443905390218997		
H 0.497012567535054 0.9247340386709353 -0.7538297483507286		

(continues on next page)

(continued from previous page)

```

H -1.049427360359161 0.0320094307806696      -0.7537906795101232
H 1.760678843023289 -1.264262738726653      -0.6572703272452628
H 0.2140471968077103 -2.156981931600252      -0.6574882069415752
H 1.207324110469442 -0.4308282262683778      -2.854859298860555
H -0.2304034502578771 -1.260970512043685      -2.855040966499596
H 1.200917269444972 -2.079821003490794      -2.803581935602674

End

GuessBonds True
Charge 2.0
End

Engine ForceField
  GuessCharges True
EndEngine

eor

# Charges are now both specified on input and also Guessed
# The values on the input (ForceField.Charge) are on purpose unreasonable
# The Guessed charges have a higher priority and the input values are ignored
# The output is a bit confusing as unused ForceField.Charge is printed

export AMS_JOBNAME=C2H10N2++.inputandguessed

rm -rf $AMS_JOBNAME.results

"$AMSBIN/ams" << eor

Task GeometryOptimization

Properties Charges=yes

GeometryOptimization
  Convergence Gradients=1.0e-6
End

System
  Atoms
    N -0.005073166519502884 0.008770355996886468      1.060120635725228      ForceField.
  ↵ Charge=-1.224106970135964811E+000
    C -0.003379615065181385 0.005774705419397744      -0.4323726711546611      ↵
  ↵ ForceField.Charge=0.481803346892513140E-001
    C 0.7147029862216027 -1.238161594687982      -0.9787933548287219      ↵
  ↵ ForceField.Charge=0.481357488383262755E-001
    N 0.7166487936613554 -1.241183181538415      -2.471469363728673      ↵
  ↵ ForceField.Charge=-0.224111043229265006E+000
    H -0.489254727061788 0.8470579056083724      1.393322418122902      ↵
  ↵ ForceField.Charge=1.327048167700910608E+000
    H 0.9419603270459358 0.02859511576851682      1.443864570589139      ↵
  ↵ ForceField.Charge=0.312019677649949589E+000
    H -0.4954439060007188 -0.801643243084588      1.443905390218997      ↵
  ↵ ForceField.Charge=0.312016700963803795E+000
    H 0.497012567535054 0.9247340386709353      -0.7538297483507286      ↵
  ↵ ForceField.Charge=0.112420754799849087E+000

```

(continues on next page)

(continued from previous page)

H -1.049427360359161 0.0320094307806696	-0.7537906795101232	✉
↪ForceField.Charge=0.112425859786873958E+000		
H 1.760678843023289 -1.264262738726653	-0.6572703272452628	✉
↪ForceField.Charge=0.112415997624231642E+000		
H 0.2140471968077103 -2.156981931600252	-0.6574882069415752	✉
↪ForceField.Charge=0.112419970108937881E+000		
H 1.207324110469442 -0.4308282262683778	-2.854859298860555	✉
↪ForceField.Charge=0.312043881750391661E+000		
H -0.2304034502578771 -1.260970512043685	-2.855040966499596	✉
↪ForceField.Charge=0.312048243703216099E+000		
H 1.200917269444972 -2.079821003490794	-2.803581935602674	✉
↪ForceField.Charge=0.327042675749500744E+000		
End		
GuessBonds True		
Charge 2.0		
End		
Engine ForceField		
GuessCharges True		
EndEngine		
eor		
# Charges obtained with Load Charges from a DFTB calc.		
export AMS_JOBNAME=C2H10N2++.dftb		
rm -rf \$AMS_JOBNAME.results		
"\$AMSBIN/ams" << eor		
Task SinglePoint		
Properties Charges=yes		
GeometryOptimization		
Convergence Gradients=1.0e-6		
End		
System		
Atoms		
N -0.005073166519502884 0.008770355996886468 1.060120635725228		
C -0.003379615065181385 0.005774705419397744 -0.4323726711546611		
C 0.7147029862216027 -1.238161594687982 -0.9787933548287219		
N 0.7166487936613554 -1.241183181538415 -2.471469363728673		
H -0.489254727061788 0.8470579056083724 1.393322418122902		
H 0.9419603270459358 0.02859511576851682 1.443864570589139		
H -0.4954439060007188 -0.801643243084588 1.443905390218997		
H 0.497012567535054 0.9247340386709353 -0.7538297483507286		
H -1.049427360359161 0.0320094307806696 -0.7537906795101232		

(continues on next page)

(continued from previous page)

```

H 1.760678843023289 -1.264262738726653 -0.6572703272452628
H 0.2140471968077103 -2.156981931600252 -0.6574882069415752
H 1.207324110469442 -0.4308282262683778 -2.854859298860555
H -0.2304034502578771 -1.260970512043685 -2.855040966499596
H 1.200917269444972 -2.079821003490794 -2.803581935602674

End

Charge 2.0
End

Engine DFTB
EndEngine

eor

loadChargeFile='C2H10N2++.dftb.results/dftb.rkf'

export AMS_JOBNAME=C2H10N2++.loaded

rm -rf $AMS_JOBNAME.results

"$AMSBIN/ams" << eor

Task GeometryOptimization

Properties Charges=yes

GeometryOptimization
  Convergence Gradients=1.0e-6
End

System
  Atoms
    N -0.005073166519502884 0.008770355996886468 1.060120635725228
      C -0.003379615065181385 0.005774705419397744 -0.4323726711546611
      C 0.7147029862216027 -1.238161594687982 -0.9787933548287219
      N 0.7166487936613554 -1.241183181538415 -2.471469363728673
      H -0.489254727061788 0.8470579056083724 1.393322418122902
      H 0.9419603270459358 0.02859511576851682 1.443864570589139
      H -0.4954439060007188 -0.801643243084588 1.443905390218997
      H 0.497012567535054 0.9247340386709353 -0.7538297483507286
      H -1.049427360359161 0.0320094307806696 -0.7537906795101232
      H 1.760678843023289 -1.264262738726653 -0.6572703272452628
      H 0.2140471968077103 -2.156981931600252 -0.6574882069415752
      H 1.207324110469442 -0.4308282262683778 -2.854859298860555
      H -0.2304034502578771 -1.260970512043685 -2.855040966499596
      H 1.200917269444972 -2.079821003490794 -2.803581935602674

    End

    GuessBonds True
    Charge 2.0
  End

Engine ForceField
  LoadCharges

```

(continues on next page)

(continued from previous page)

```

File $loadChargeFile
End
EndEngine

eor

# Charges are now both specified on input and also Guessed
# The values on the input (ForceField.Charge) are on purpose unreasonable
# The Guessed charges have a higher priority and the input values are ignored
# The output is a bit confusing as unused ForceField.Charge is printed

export AMS_JOBNAME=C2H10N2++.inputandloaded

rm -rf $AMS_JOBNAME.results

"$AMSBIN/ams" << eor

Task GeometryOptimization

Properties Charges=yes

GeometryOptimization
  Convergence Gradients=1.0e-6
End

System
  Atoms
    N -0.005073166519502884 0.008770355996886468  1.060120635725228  ForceField.
    ↵Charge=-1.224106970135964811E+000
      C -0.003379615065181385 0.005774705419397744 -0.4323726711546611 ↵
    ↵ForceField.Charge=0.481803346892513140E-001
      C 0.7147029862216027 -1.238161594687982 -0.9787933548287219 ↵
    ↵ForceField.Charge=0.481357488383262755E-001
      N 0.7166487936613554 -1.241183181538415 -2.471469363728673 ↵
    ↵ForceField.Charge=-0.224111043229265006E+000
      H -0.489254727061788 0.8470579056083724 1.393322418122902 ↵
    ↵ForceField.Charge=1.327048167700910608E+000
      H 0.9419603270459358 0.02859511576851682 1.443864570589139 ↵
    ↵ForceField.Charge=0.312019677649949589E+000
      H -0.4954439060007188 -0.801643243084588 1.443905390218997 ↵
    ↵ForceField.Charge=0.312016700963803795E+000
      H 0.497012567535054 0.9247340386709353 -0.7538297483507286 ↵
    ↵ForceField.Charge=0.112420754799849087E+000
      H -1.049427360359161 0.0320094307806696 -0.7537906795101232 ↵
    ↵ForceField.Charge=0.112425859786873958E+000
      H 1.760678843023289 -1.264262738726653 -0.6572703272452628 ↵
    ↵ForceField.Charge=0.112415997624231642E+000
      H 0.2140471968077103 -2.156981931600252 -0.6574882069415752 ↵
    ↵ForceField.Charge=0.112419970108937881E+000
      H 1.207324110469442 -0.4308282262683778 -2.854859298860555 ↵
    ↵ForceField.Charge=0.312043881750391661E+000
      H -0.2304034502578771 -1.260970512043685 -2.855040966499596 ↵
    ↵ForceField.Charge=0.312048243703216099E+000
      H 1.200917269444972 -2.079821003490794 -2.803581935602674 ↵
    ↵ForceField.Charge=0.327042675749500744E+000
      End

```

(continues on next page)

(continued from previous page)

```

    GuessBonds True
    Charge 2.0
End

Engine ForceField
    LoadCharges
        File $loadChargeFile
    End
EndEngine

eor

# this calculation should succeed, ignoring the default zero total charge and using
→the atomic charges instead

export AMS_JOBNAME=C2H10N2++.warning

rm -rf $AMS_JOBNAME.results

"$AMSBIN/ams" << eor

Task GeometryOptimization

Properties Charges=yes

GeometryOptimization
    Convergence Gradients=1.0e-6
End

System
    Atoms
        N -0.005073166519502884 0.008770355996886468    1.060120635725228    ForceField.
    ↪Charge=-0.224106970135964811E+000
        C -0.003379615065181385 0.005774705419397744 -0.4323726711546611    ↪
    ↪ForceField.Charge=0.481803346892513140E-001
        C 0.7147029862216027 -1.238161594687982      -0.9787933548287219    ↪
    ↪ForceField.Charge=0.481357488383262755E-001
        N 0.7166487936613554 -1.241183181538415      -2.471469363728673    ↪
    ↪ForceField.Charge=-0.224111043229265006E+000
        H -0.489254727061788 0.8470579056083724      1.393322418122902    ↪
    ↪ForceField.Charge=0.327048167700910608E+000
        H 0.9419603270459358 0.02859511576851682      1.443864570589139    ↪
    ↪ForceField.Charge=0.312019677649949589E+000
        H -0.4954439060007188 -0.801643243084588      1.443905390218997    ↪
    ↪ForceField.Charge=0.312016700963803795E+000
        H 0.497012567535054 0.9247340386709353      -0.7538297483507286    ↪
    ↪ForceField.Charge=0.112420754799849087E+000
        H -1.049427360359161 0.0320094307806696      -0.7537906795101232    ↪
    ↪ForceField.Charge=0.112425859786873958E+000
        H 1.760678843023289 -1.264262738726653      -0.6572703272452628    ↪
    ↪ForceField.Charge=0.112415997624231642E+000
        H 0.2140471968077103 -2.156981931600252      -0.6574882069415752    ↪
    ↪ForceField.Charge=0.112419970108937881E+000
        H 1.207324110469442 -0.4308282262683778      -2.854859298860555    ↪
    ↪ForceField.Charge=0.312043881750391661E+000

```

(continues on next page)

(continued from previous page)

```

H -0.2304034502578771 -1.260970512043685      -2.855040966499596 ▾
˓→ForceField.Charge=0.312048243703216099E+000
H 1.200917269444972 -2.079821003490794      -2.803581935602674 ▾
˓→ForceField.Charge=0.327042675749500744E+000
End

GuessBonds True
End

Engine ForceField
EndEngine

eor

# this calculation should trigger a warning because the explicitly set Charge doesn't
˓→match

export AMS_JOBNAME=C2H10N2++.warning

rm -rf $AMS_JOBNAME.results

"$AMSBIN/ams" << eor

Task GeometryOptimization

Properties Charges=yes

GeometryOptimization
  Convergence Gradients=1.0e-6
End

System
  Atoms
    N -0.005073166519502884 0.008770355996886468   1.060120635725228   ForceField.
˓→Charge=-0.224106970135964811E+000
    C -0.003379615065181385 0.005774705419397744 -0.4323726711546611 ▾
˓→ForceField.Charge=0.481803346892513140E-001
    C 0.7147029862216027 -1.238161594687982      -0.9787933548287219 ▾
˓→ForceField.Charge=0.481357488383262755E-001
    N 0.7166487936613554 -1.241183181538415      -2.471469363728673 ▾
˓→ForceField.Charge=-0.224111043229265006E+000
    H -0.489254727061788 0.8470579056083724      1.393322418122902 ▾
˓→ForceField.Charge=0.327048167700910608E+000
    H 0.9419603270459358 0.02859511576851682      1.443864570589139 ▾
˓→ForceField.Charge=0.312019677649949589E+000
    H -0.4954439060007188 -0.801643243084588      1.443905390218997 ▾
˓→ForceField.Charge=0.312016700963803795E+000
    H 0.497012567535054 0.9247340386709353      -0.7538297483507286 ▾
˓→ForceField.Charge=0.112420754799849087E+000
    H -1.049427360359161 0.0320094307806696      -0.7537906795101232 ▾
˓→ForceField.Charge=0.112425859786873958E+000
    H 1.760678843023289 -1.264262738726653      -0.6572703272452628 ▾
˓→ForceField.Charge=0.112415997624231642E+000
    H 0.2140471968077103 -2.156981931600252      -0.6574882069415752 ▾
˓→ForceField.Charge=0.112419970108937881E+000

```

(continues on next page)

(continued from previous page)

```

H 1.207324110469442 -0.4308282262683778      -2.854859298860555  ↴
↳ForceField.Charge=0.312043881750391661E+000
      H -0.2304034502578771 -1.260970512043685      -2.855040966499596  ↴
↳ForceField.Charge=0.312048243703216099E+000
      H 1.200917269444972 -2.079821003490794      -2.803581935602674  ↴
↳ForceField.Charge=0.327042675749500744E+000
      End

      GuessBonds True
      Charge 1.0
End

Engine ForceField
EndEngine

eor

# finally let us make on purpose an error (total charge not set with strict checking)
↳enabled)
# this calculation is supposed to fail, and not print an energy

echo "The following error is intended"

export AMS_JOBNAME=C2H10N2++.inputerror

rm -rf $AMS_JOBNAME.results

"$AMSBIN/ams" << eor

Task GeometryOptimization

Properties Charges=yes

GeometryOptimization
  Convergence Gradients=1.0e-6
End

System
  Atoms
    N -0.005073166519502884 0.008770355996886468  1.060120635725228  ForceField.
    ↳Charge=-0.224106970135964811E+000
      C -0.003379615065181385 0.005774705419397744 -0.4323726711546611  ↴
    ↳ForceField.Charge=0.481803346892513140E-001
      C 0.7147029862216027 -1.238161594687982      -0.9787933548287219  ↴
    ↳ForceField.Charge=0.481357488383262755E-001
      N 0.7166487936613554 -1.241183181538415      -2.471469363728673  ↴
    ↳ForceField.Charge=-0.224111043229265006E+000
      H -0.489254727061788 0.8470579056083724      1.393322418122902  ↴
    ↳ForceField.Charge=0.327048167700910608E+000
      H 0.9419603270459358 0.02859511576851682      1.443864570589139  ↴
    ↳ForceField.Charge=0.312019677649949589E+000
      H -0.4954439060007188 -0.801643243084588      1.443905390218997  ↴
    ↳ForceField.Charge=0.312016700963803795E+000
      H 0.497012567535054 0.9247340386709353      -0.7538297483507286  ↴
    ↳ForceField.Charge=0.112420754799849087E+000
      H -1.049427360359161 0.0320094307806696      -0.7537906795101232  ↴
    ↳ForceField.Charge=0.112425859786873958E+000
      (continues on next page)

```

(continued from previous page)

```

H 1.760678843023289 -1.264262738726653 -0.6572703272452628 ↵
↳ForceField.Charge=0.112415997624231642E+000
H 0.2140471968077103 -2.156981931600252 -0.6574882069415752 ↵
↳ForceField.Charge=0.112419970108937881E+000
H 1.207324110469442 -0.4308282262683778 -2.854859298860555 ↵
↳ForceField.Charge=0.312043881750391661E+000
H -0.2304034502578771 -1.260970512043685 -2.855040966499596 ↵
↳ForceField.Charge=0.312048243703216099E+000
H 1.200917269444972 -2.079821003490794 -2.803581935602674 ↵
↳ForceField.Charge=0.327042675749500744E+000
End

GuessBonds True
End

Engine ForceField
DoChargeCheck True
EndEngine

eor

```

## 5.3 Example: load partial charges from another engine

You can use [LoadCharges](#) (page 14) to load charges from another calculation. The key [GuessCharges](#) (page 13) is a simplified version of this, being more convenient, but less flexible.

Download `LoadCharges.run`

```

#!/bin/sh

# First we calculate the charges for a system

# Here we use the dftb engine, but any engine can be used for this purpose

export AMS_JOBNAME=CalculateCharges

rm -rf $AMS_JOBNAME.results

$AMSBIN/ams << eor
Task SinglePoint

Properties Charges=yes

System
Atoms
C 0.0 0.0 0.0
O 1.13 0.0 0.0
C 0.0 0.0 2.0
O 1.13 0.0 2.0
End
End

```

(continues on next page)

(continued from previous page)

```

Engine DFTB
EndEngine

eor

# let us first optimize without charges

export AMS_JOBNAME=DoNotUseCharges

rm -rf $AMS_JOBNAME.results

$AMSBIN/ams << eor
Task GeometryOptimization

GeometryOptimization
  Convergence Step=1.0e-3
End

System
  Atoms
    C 0.0 0.0 0.0
    O 1.13 0.0 0.0
    C 0.0 0.0 2.1
    O 1.13 0.0 1.9
  End
End

Engine ForceField
EndEngine

eor

# Now that we have charges from our previous fancy calculation, let us use them for a
→UFF geometry optimization
# * The name of the file depends on the engine used (in this case dftb.rkf)
# * The geometry does not need to be the same

export AMS_JOBNAME=LoadCharges

rm -rf $AMS_JOBNAME.results

$AMSBIN/ams << eor
Task GeometryOptimization

GeometryOptimization
  Convergence Step=1.0e-3
End

System
  Atoms
    C 0.0 0.0 0.0
    O 1.13 0.0 0.0
    C 0.0 0.0 2.1
    O 1.13 0.0 1.9
  End
End

```

(continues on next page)

(continued from previous page)

```

Engine ForceField
  Verbosity Verbose
  LoadCharges File=CalculateCharges.results/dftb.rkf
EndEngine

eor

# Finally let us use the charge guessing, by default dftb is used for charge guessing

export AMS_JOBNAME=GuessCharges

rm -rf $AMS_JOBNAME.results

$AMSBIN/ams << eor
Task GeometryOptimization

GeometryOptimization
  Convergence Step=1.0e-3
End

System
  Atoms
    C 0.0 0.0 0.0
    O 1.13 0.0 0.0
    C 0.0 0.0 2.1
    O 1.13 0.0 1.9
  End
End

Engine ForceField
  Verbosity Verbose
  GuessCharges True
EndEngine

eor

```

## 5.4 Example: load atom types from a previous run

You can load the atom types from another force field calculation.

Observe that this is done with the `LoadForceFieldAtomTypes` inside the `System` block, see the [System definition section of the AMS manual](#).

Download `LoadTypes.run`

```

#!/bin/sh

# In this example we use the amber forcefield that cannot guess atom types

# First we "calculate" the types

# We do this by specifying them as atom attributes (ForceField.Type)

export AMS_JOBNAME=CalculateTypes

```

(continues on next page)

(continued from previous page)

```

rm -rf $AMS_JOBNAME.results

$AMSBIN/ams << eor
Task GeometryOptimization

Properties Charges=yes

System
  Atoms
    C      1.94807   3.58290  -0.58162      ForceField.Charge=0.0      ForceField.
  ↳Type=CT
    H      1.69949   4.49893  -1.05273      ForceField.Charge=0.0      ForceField.
  ↳Type=HC
    H      2.99455   3.17964  -0.86304      ForceField.Charge=0.0      ForceField.
  ↳Type=HC
    C      0.94659   2.40054  -0.92364      ForceField.Charge=0.0      ForceField.
  ↳Type=CT
    C      1.94191   3.61595  1.09448      ForceField.Charge=0.0      ForceField.
  ↳Type=CT
    N     -1.74397  -3.46417  0.31178      ForceField.Charge=-0.9530  ForceField.
  ↳Type=N2
    C     -1.00720  -2.20758  0.33536      ForceField.Charge=0.8185  ForceField.
  ↳Type=CA
    C     -1.66928  -1.00652  0.31001      ForceField.Charge=-0.5215  ForceField.
  ↳Type=CM
    C     -0.92847   0.25653  0.34895      ForceField.Charge=0.0053  ForceField.
  ↳Type=CM
    N      0.43971   0.26735  0.38232      ForceField.Charge=-0.0484  ForceField.
  ↳Type=N*
    N      0.36409  -2.20477  0.28992      ForceField.Charge=-0.7584  ForceField.
  ↳Type=NC
    C      1.09714  -0.95413  0.22469      ForceField.Charge=0.7538  ForceField.
  ↳Type=C
    H     -2.89781  -3.50815  0.31746      ForceField.Charge=0.4234  ForceField.
  ↳Type=H
    H     -1.21484  -4.49217  0.31721      ForceField.Charge=0.4234  ForceField.
  ↳Type=H
    H     -2.80940  -0.93497  0.30550      ForceField.Charge=0.1928  ForceField.
  ↳Type=HA
    H     -1.55324   1.21497  0.33885      ForceField.Charge=0.1958  ForceField.
  ↳Type=H4
    C      1.23309   1.44017  0.30994      ForceField.Charge=0.0066  ForceField.
  ↳Type=CT
    O      2.58277  -1.01636  0.23914      ForceField.Charge=-0.6252  ForceField.
  ↳Type=O
    H      2.37276   1.25557  0.29984      ForceField.Charge=0.2902  ForceField.
  ↳Type=H2
    O      1.02358   2.43085  1.50880      ForceField.Charge=-0.2033  ForceField.
  ↳Type=OS
    H      1.17136   1.95097  -1.87367      ForceField.Charge=0.0      ForceField.
  ↳Type=HC
    H     -0.10600   2.77333  -0.80348      ForceField.Charge=0.0      ForceField.
  ↳Type=HC
    H      1.62170   4.54039  1.51392      ForceField.Charge=0.0      ForceField.
  ↳Type=H1
    H      2.99608   3.28749  1.41345      ForceField.Charge=0.0      ForceField.
  ↳Type=H1

```

(continues on next page)

(continued from previous page)

```

    End
End

Engine ForceField
    Type Amber95
EndEngine

eor

# Now we load the types from the previous result

# The result should be identical to the first calculation

export AMS_JOBNAME=LoadTypes

rm -rf $AMS_JOBNAME.results

$AMSBIN/ams << eor
Task GeometryOptimization

System
Atoms
    C      1.94807   3.58290  -0.58162
    H      1.69949   4.49893  -1.05273
    H      2.99455   3.17964  -0.86304
    C      0.94659   2.40054  -0.92364
    C      1.94191   3.61595  1.09448
    N     -1.74397  -3.46417  0.31178
    C     -1.00720  -2.20758  0.33536
    C     -1.66928  -1.00652  0.31001
    C     -0.92847   0.25653  0.34895
    N      0.43971   0.26735  0.38232
    N      0.36409  -2.20477  0.28992
    C      1.09714  -0.95413  0.22469
    H     -2.89781  -3.50815  0.31746
    H     -1.21484  -4.49217  0.31721
    H     -2.80940  -0.93497  0.30550
    H     -1.55324   1.21497  0.33885
    C      1.23309   1.44017  0.30994
    O      2.58277  -1.01636  0.23914
    H      2.37276   1.25557  0.29984
    O      1.02358   2.43085  1.50880
    H      1.17136   1.95097  -1.87367
    H     -0.10600   2.77333  -0.80348
    H      1.62170   4.54039  1.51392
    H      2.99608   3.28749  1.41345
End
LoadForceFieldCharges    file=CalculateTypes.results
LoadForceFieldAtomTypes  file=CalculateTypes.results
End

Engine ForceField
    Type Amber95
    Verbosity Verbose

EndEngine

```

(continues on next page)

(continued from previous page)

eor

## 5.5 Example: using amber or tripos

Download 2h2o.run

```
#!/bin/sh

AMS_JOBNAME=amber95 $AMSBIN/ams << eor

Task SinglePoint

System
Atoms
    O      0.0000    0.0000    0.0000    ForceField.Type=OW    ForceField.
    ↵Charge=-0.8340
        H     -0.5220    0.2660   -0.7570    ForceField.Type=HW    ForceField.
    ↵Charge=0.4170
        H     -0.5220    0.2660    0.7570    ForceField.Type=HW    ForceField.
    ↵Charge=0.4170
        O      0.0000   -3.2000    0.0000    ForceField.Type=OW    ForceField.
    ↵Charge=-0.8340
        H      0.0570   -2.2440    0.0000    ForceField.Type=HW    ForceField.
    ↵Charge=0.4170
        H      0.9110   -3.4950    0.0000    ForceField.Type=HW    ForceField.
    ↵Charge=0.4170
    End
BondOrders
    1  2  1.0
    1  3  1.0
    4  5  1.0
    4  6  1.0
End
End

Engine ForceField
    Type Amber95
EndEngine
eor

AMS_JOBNAME=tripos5.2 $AMSBIN/ams << eor

Task SinglePoint

System
Atoms
    O      0.0000    0.0000    0.0000    ForceField.Type=O.3    ForceField.
    ↵Charge=-0.8340
        H     -0.5220    0.2660   -0.7570    ForceField.Type=H    ForceField.
    ↵Charge=0.4170
        H     -0.5220    0.2660    0.7570    ForceField.Type=H    ForceField.
    ↵Charge=0.4170
```

(continues on next page)

(continued from previous page)

```

O      0.0000   -3.2000    0.0000   ForceField.Type=O..3   ForceField.
↪Charge=-0.8340
H      0.0570   -2.2440    0.0000   ForceField.Type=H   ForceField.
↪Charge=0.4170
H      0.9110   -3.4950    0.0000   ForceField.Type=H   ForceField.
↪Charge=0.4170
End
BondOrders
  1 2 1.0
  1 3 1.0
  4 5 1.0
  4 6 1.0
End
End

Engine ForceField
  Type Tripos5.2
EndEngine
eor

```

## 5.6 Example: calculate some simple properties for water

Download `water_properties.run`

```

#!/bin/sh

$AMSBIN/ams << eor

Task GeometryOptimization

Properties
  BondOrders Yes
  Charges Yes
  DipoleMoment Yes
  NormalModes Yes
End

System
  Atoms
    O  0.0000  0.0000  0.0000  ForceField.Type=OW  ForceField.Charge=-0.8340
    H -0.5220  0.2660 -0.7570  ForceField.Type=HW  ForceField.Charge=0.4170
    H -0.5220  0.2660  0.7570  ForceField.Type=HW  ForceField.Charge=0.4170
  End
  BondOrders
    1 2 1.0
    1 3 1.0
  End
End

Engine ForceField
  Type Amber95
  ForceFieldFile $AMSRSCOURCES/ForceFields/amber95.ff
EndEngine

```

(continues on next page)

(continued from previous page)

```
eor

echo "MM Charges:"
$AMSBIN/amsreport ams.results/forcefield.rkf -r "AMSResults%Charges"
```

## 5.7 Example: single point for ammonia with TRIPoS

Download Ammonia\_Tripos.run

```
#!/bin/sh

#
# This is a technical example comparing analytical and numerical gradients for the
# →Tripos forcefield
#
# The allowMissingParameters is a trick to run this molecule even though it is not
# →fully supported by the definition file
#

for num in no yes
do

export AMS_JOBNAME=tripos3.num=$num

rm -rf $AMS_JOBNAME.results

$AMSBIN/ams << eor

Task SinglePoint
Properties Gradients=yes

EngineDebugging IgnoreGradientsRequest=$num IgnorePreviousResults=true

NumericalDifferentiation NuclearStepSize=1.0e-4

System
Atoms
    N      0.00000000      0.00000000      0.26448000  ForceField.Charge=0.0
    ↪ForceField.Type=N.2
    H      -0.48379000      0.83795000     -0.08816000  ForceField.Charge=0.0
    ↪ForceField.Type=H
    H      -0.48379000     -0.83795000     -0.08816000  ForceField.Charge=0.0
    ↪ForceField.Type=H
    H      0.96758000     -0.00000000     -0.08816000  ForceField.Charge=0.0
    ↪ForceField.Type=H
    End

BondOrders
    1 2 1.0
    1 3 1.0
    1 4 1.0
End
End
```

(continues on next page)

(continued from previous page)

```
Engine ForceField
  Type Tripos5.2
  AllowMissingParameters yes
EndEngine
eor

done
```

---

CHAPTER  
SIX

---

## REQUIRED CITATIONS

When you publish results in the scientific literature that were obtained with programs of the AMS package, you are required to include references to the program package with the appropriate release number, and a few key publications.

**For calculations with the UFF4MOF parameters:** M.A. Addicoat, N. Vankova, I.F. Akter, and T. Heine, *An extension of the Universal Force Field to Metal-Organic Frameworks*, *J. Chem. Theory Comput.* 10, 880-891 (2013) (<https://doi.org/10.1021/ct400952t>)

**For calculations with the UFF4MOFII parameters:** D.E. Coupry, M.A. Addicoat, and T. Heine, *An Extension of the Universal Force Field for Metal-Organic Frameworks*, *J. Chem. Theory Comput.* 12, 5215-5225 (2016) (<https://doi.org/10.1021/acs.jctc.6b00664>)

**For calculations with the APPLE&P forcefield:**

O. Borodin, *Polarizable Force Field Development and Molecular Dynamics Simulations of Ionic Liquids*, *J. Phys. Chem. B* 113, 11463–11478 (2009) (<https://doi.org/10.1021/jp905220k>)

### 6.1 External programs and libraries

[Click here](#) for the list of programs and/or libraries used in the AMS package. On some platforms optimized libraries have been used and/or vendor specific MPI implementations.



## PARAMETER FILES

The parameters of a forcefield are defined via one or more files, automatically set when using a standard *type* (page 9). One way to change it is to use a parametrization made by someone else, that works better for systems of your interest. A far more advanced use is to tweak an existing file, or create a new one, possibly to improve the results for specific systems of interest. For such a project the PARAMS tool might be helpful.

Here we distinguish the UFF and the AMBER case.

### 7.1 UFF parameters

The parameter set used by UFF can be changed via the *UFF* (page 15) key block. Aside from the standard UFF forcefield, we ship two parameter sets for Metal-Organic Frameworks:

#### UFF4MOF parameters

We ship the extended parameter set for Metal-Organic Frameworks created by M.A. Addicoat et al. (2013). Select the UFF4MOF\_general\_db, UFF4MOF\_elements\_db and UFF4MOF\_mmatomtypes\_db files to use these parameters, and check that the proper atom types are detected for your system or set them manually. Please see [7 (page 59)] for details on the parameters.

#### UFF4MOFII parameters

We ship a second extended parameter set for Metal-Organic Frameworks created by D.E. Coupry et al. (2016). Select the UFF4MOFII\_general\_db, UFF4MOFII\_elements\_db and UFF4MOFII\_mmatomtypes\_db files to use these parameters, and check that the proper atom types are detected for your system or set them manually. Please see [8 (page 59)] for details on the parameters.

#### 7.1.1 User-modified force fields (expert option)

Finding good UFF parameters can be a challenging task, and any results with modified parameters should be checked very carefully. SCM has no experience with this, and the parameters supplied for UFF have not been generated by us. Feel free to test new parameters, and feel free to let us know if you have a good working set for a specialized situation.

##### General parameters file

The general\_db file (\$AMSHOME/atomicdata/UFF/general\_db) contains all the parameters used to calculate the forces and energies. The format is:

MMAAtomType, ri, phi, xi, di, psi, zmm, vsp3, vsp2, chi, nc.

The items in the list are:

- MMAAtomType: name, max 5 characters

- ri: Valence Bond [ $\text{\AA}$ ]
- phi: Valence Angle [Degree]
- xi: Nonbond Distance [ $\text{\AA}$ ]
- di: Nonbond Energy [kcal/mol]
- psi: Nonbond scale [Number]
- zmm: Effective Charge [Charge]
- vsp3: sp3 Torsional Barrier [kcal/mol]
- vsp2: sp2 Torsional Barrier [kcal/mol]
- chi: Electronegativity
- nc: Number of directly attached atoms, aka coordination number. This is required for counting the number of possible dihedrals, and is defined only for the sp2 and sp3 centers (types 2, R, and 3)

The current set of parameters comes from the deMonNano program, and is a combination of published parameters and fitted data to fill in the gaps. The deMonNano documentation says the following about the parameters:

### Implementation of the Universal Force Field (UFF) in deMonNano

---

As far as possible, UFF molecular mechanics forcefield in deMon follows the published forcefield definition in [1]. In several cases, the definitions and expressions in [1] are not consistent with the published applications of the forcefield [1,5,6]. In those cases, an attempt was made to correct the errors and omissions, using information from [2].

The following changes were made, compared to the published UFF forcefield description (all equations and page numbers refer to [1]).

1. Sign error in Eq. 2 (equilibrium bond length) was corrected  
- electronegativity correction must be negative!
2. Equilibrium valence angle for O\_3\_z was corrected from 146.0 degree to 145.45 degree.
3. Bending periodicity (Eq. 10) for linear coordination was corrected from 1 to 2.
4. Sign errors were corrected in eqs. 13 and unnumbered equation for the beta parameter (between eqs. 13 and 14).
5. The reference value of the UFF amide force constant, of 105.5 kcal/mol/rad\*\*2 (p. 10028) is wrong. The results are consistent with the force constant of 211.0 kcal/mol/rad\*\*2.
6. Equilibrium torsional angle for a bond between a group-6A atom (oxygen ...) and an sp2 atom (90 degree) is wrong (p. 10028). It should be 0 degree.
7. The conditional for the special-case sp2-sp3 torsion (p. 10029) is wrong, and should be inverted - see [4].
8. The overall shape of the UFF torsional potential degenerates to

(continues on next page)

(continued from previous page)

- a Heavyside function when one of the bond angles becomes linear, leading to failures in geometry optimization and force constant evaluation. The UFF torsional term was augmented with a smooth masking function, to avoid this.
- UFF inversion potential is not defined in [1] for group 5A elements (from phosphorus down). Taking the equilibrium inversion coordinate of 87 degree, and the suitable expressions for the cosine weights (see `uff_get_inversion_shape` in "uff\_database.f90") appears to reproduce published UFF structures and energetics.

The following atom types have been fully tested, and are believed to reproduce published UFF forcefield results exactly. The examples refer to the \$deMon/examples/test.mm directory.

Atom type	Example	Description
A13	alme3tma	Trivalent aluminum
As3+3	ASF3	Trivalent arsenic
B_2	bcl3	Planar (sp <sup>2</sup> ) boron
B_3	b2h5nme2	Tetrahedral (sp <sup>2</sup> ) boron, including charge transfer adducts and borohydrates
Br	bbr3	Univalent bromine
C_1	c2h2, co	Linear (sp) carbon
C_2	acetone	Planar tricoordinated (sp <sup>2</sup> ) carbon
C_3	c2h6	Tetrahedral (sp <sup>3</sup> ) carbon
C_R	c4h6	Resonant, variable bond order (sp <sup>2</sup> ) carbon.
C1	socl2	Univalent chlorine
F_-	sof2ncl	Univalent fluorine
Ge3	geh3ogegeh3	Tetrahedral (sp <sup>3</sup> ) germanium
H_-	h2o	Normal, non-bridging hydrogen
H_b	b2h5nme2	Bridging hydrogen, for use in boranes (NOT SUITABLE FOR H-BONDS!)
I_-	bi3	Univalent iodine
N_1	ch3cn	Monocoordinated (sp) nitrogen, triple bond
N_2	ch3n2ch3	Dicoordinated (sp <sup>2</sup> ) nitrogen, single-double bond
N_3	ch3nh2	Amine (sp <sup>3</sup> ) nitrogen, three single bonds
N_3+4	b2h5nme2	Charged amine (sp <sup>3</sup> ) nitrogen, four single bonds (THIS IS NOT A STANDARD UFF TYPE!)
N_R	c5h5n	Resonant planar (sp <sup>2</sup> ) nitrogen, for use in aromatics and amides. For amides, use 1.41 bond order!
O_1	co	Special "co" type, one triple bond.
O_2	acetone	One-coordinated (sp <sup>2</sup> ) oxygen, one double bond.
O_3	h2o	Two-coordinated (sp <sup>3</sup> ) oxygen, two single bonds
O_3_z	sih3osih3	Special two-coordinated oxygen, for use in Si-O bonds
O_R	c4h4o	Resonant planar (sp <sup>2</sup> ) oxygen, also for use in nitro groups and such.
P_3+3	ph3	Pyramidal (sp <sup>3</sup> ) phosphorus, three single bonds
P_3+5	p4o7	Tetrahedral hypervalent phosphorus
P_3+q	bh3ph3	Dative tetrahedral (sp <sup>3</sup> ) phosphorus, watch for the bond order!
S_3+2	ch3sch3	Bent two-coordinated sulfur (sp <sup>3</sup> ), two single bonds
S_3+4	socl2	Pyramidal three-coordinated hypervalent sulfur
S_3+6	so2cl2	Tetrahedral four-coordinated hypervalent sulfur

(continues on next page)

(continued from previous page)

Se3+2	h2se	Bent two-coordinated (sp <sup>3</sup> ) selenium
Si3	si4o4h8	Tetrahedral silicon

Additionally, parameter sets for the following atom types are believed be complete, and may be expected produce results identical to the published UFF data: Li, Na, K\_, Rb, Cs (Note that UFF does not specify atomic charges - it is your responsibility to assign those, if charges are needed!)

For the remaining atom types, UFF definition [1] relies on an unpublished set of electronegativities [2]. In deMon, these values were replaced by Pauling electronegativities, scaled to fit published UFF electronegativities. This can be expected to produce small deviations in bond lengths and bond angles, compared to published UFF results.

If you wish to use other parameters, you should copy the general\_db file, and rename it. This new file can also be placed outside of \$AMSHOME/atomicdata/UFF.

### Elements file

The elements\_db file holds all the elements known to UFF. Keep in mind that these are not the MMAtomTypes, but pure chemical elements. The table contains for every element: atomic number, symbol, minimal valence number, maximum valence number, minimal bond order, maximal bond order. The data in the elements\_db is mainly used for cleaning up the Pauling bond orders guessed by UFF, and will probably not need to be modified.

### MM Atom Types file

The mmatomtypes\_db file contains the matching rules for assigning MM atom types to chemical elements, based on their valence number, and the number of neighbor (bonded) atoms. The current implementation of UFF is limited to 6 MM atom types per element. The table contains for every MM atom type: Number of the element it belongs to, the i-th type of this element, the valence number corresponding to this MM atom type, number of neighbors this MM atom type has, the name of this MM atom type. The naming convention follows the original UFF paper [1]:

A five-character mnemonic label is used to describe the atom types. The first two characters correspond to the chemical symbol; an underscore appears in the second column if the symbol has one letter (e.g., N\_ is nitrogen, Rh is rhodium). The third column describes the hybridization or geometry: 1 = linear, 2 = trigonal, R = resonant, 3 = tetrahedral, 4 = square planar, 5 = trigonal bipyramidal, 6 = octahedral. Thus N\_3 is tetrahedral nitrogen, while Rh6 is octahedral rhodium. The forth and fifth columns are used as indicators of alternate parameters such as formal oxidation state: Rh6+3 indicates an octahedral rhodium formally in the +3 oxidation state, e.g., Rh(NH<sub>3</sub>)<sub>6</sub><sup>+3</sup>. H\_b indicates a bridging hydrogen as in B<sub>2</sub>H<sub>6</sub> O\_3\_z is an oxygen suited for framework oxygens of a zeolite lattice. P\_3\_q is a tetrahedral four-coordinate phosphorus used to describe organo-metallic coordinated phosphines.

You can copy the mmatomtypes\_db and change it if you need to modify the atom typing behavior of UFF.

## 7.2 AMBER parameters

If you want to use a non-standard forcefield you can specify the *ForceFieldFile* (page 15).

Currently two formats are supported for non-uff forcefields. The first is the ADF/SCM related “.ff” format. The other is the much more widely used AMBER “.dat” format.

### 7.2.1 AMBER forcefield file

The format of the AMBER “.dat” files is described here <http://ambermd.org/FileFormats.php#parm.dat>. Currently the following features are not supported

- Parameter modification files
- The torsions have extra info about 1-4 scaling for nonbonded terms, ignored
- AMBER term 8: INPUT FOR H-BOND 10-12 POTENTIAL PARAMETERS
- AMBER term 9: INPUT FOR EQUIVALENCING ATOM SYMBOLS FOR THE NON-BONDED 6-12 POTENTIAL PARAMETERS

## 7.2.2 SCM forcefield file

An example of this is `$AFDHOME/atomicdata/ForceField/amber95.ff`. It has a flexible format and is fully self documented. It is not used outside of the ADF/SCM context.

The file must contain the force field parameters and the MM potential for each kind of MM interaction. Although predefined force field files (AMBER and SYBYL) are provided, these force field files can be customized. For example, one may want to change a particular force constant, or one may need to introduce a new atom type, for instance a transition metal. This section provides a detailed description of the force field file.

### Format

The force field file is keyword driven with each key block defining parameters for each molecular mechanics interaction type such as bond types, angle types, torsion types, ... etc. The key block begins with the keyword, such as “BONDS”.

The lines that actually contain the parameters are sandwiched between two lines that contain “=====”. The lines between the keyword and the first line containing “=====” are not read by the program. These lines are intended for the user to define the columns as shown below. There can be as many lines between the keyword and the first ‘====’ as needed.

Example:

```
BONDS
Atoms  pot  K          ro      Notes
i - j  type  (kcal/molA^2) (Ang)
=====
...
CA   CA  1    938.0        1.400 amber95
CT   CT  1    620.0        1.526 amber95
...
=====
```

### Force Field Atom types

The force field atom types are the labels given to each atom in the real system, which determine all interaction parameters involving that atom.

There are some limitations to the force field label types that the user can specify:

- Labels can be a maximum of four characters long, with no spaces.
- The atom types are case sensitive.
- They can contain letters, numbers and other characters except ‘,’ ‘.’ or ‘=’ and tabs.

Example of atom types that are not compatible with the program: C.3, C 3, C=3, C\_sp3, \*

Examples of atom types that are correct: C\_3, C3, Csp3, and C\*

### Wild Cards

Wild cards can be specified with the asterisk, ‘\*’. Wild cards can be specified for angles, torsions and out-of-plane bends. Please refer to the specific sections for the limitations.

**CAUTION:** When using wild cards, place the wild cards at the beginning of the data section, beginning with the parameters with the most wild cards and ending with those that posses the least wild cards.

Example:

•	C_3	•	100.310	111.000	<i>two wild cards</i>
•	C_3	C_3	100.310	111.000	<i>one wild card</i>
C_2	C_3	C_3	100.310	111.000	<i>no wild cards</i>

If this ordering is not followed, then the wild card parameters will over-ride the specific parameters.

### Miscellaneous Notes

- Do not remove the ‘=====’ separator lines.
- Units are in kcal/mol, Angstroms, degrees, amu unless otherwise specified
- Sections can be in any order; i.e. BENDS can come before BONDS.
- All keywords are case sensitive and most are in ALL-CAPS
- Input is all free format
- Blank lines will be ignored
- Comment lines can be added to parameter data sections by beginning the line with the '#' symbol.

Example:

```
H H 1.0080
HC H 1.0080
# example of comment line denoted with # mark.
H1 H 1.0080
H2 H 1.0080
```

### A (partial) Example File

Here we provide an example force field file to illustrate the format of the file. Only a limited number of parameters are included. A detailed description of each section of the force field file is provided in the next section.

```
FORCE_FIELD_SETTINGS
=====
ELSTAT_1-4_SCALE      1.0000
VDW_1-4_SCALE         1.0000
VDW_DEFAULT_POTENTIAL 1          (1:6-12 2:exp-6 3:exp purely repulsive)
DIELECTRIC_CONSTANT   1.000
=====

MASSES & ATOM LABELS
-----
force_field atomic
atom_type   symbol mass   NOTES
=====
C_3        C     12.0110 sp3 hybridized carbon
C_2        C     12.0110 sp2 hybridized carbon
C_1        C     12.0110 sp1 hybridized carbon
C_ar      C     12.0110 aromatic
N_3        N     14.0070
```

(continues on next page)

(continued from previous page)

```

N_2           N      14.0070
O_3           O      15.9990
=====
BONDS Ebond = 0.5*K(r-ro)**2
-----
Atoms      pot
i - j      type K      R      NOTES
=====
C_2 C_2 1    1340.00 1.335 WHITE_77
C_2 C_3 1    639.00 1.501 WHITE_75
C_3 C_3 1    633.60 1.540 *
C_3 N_2 1    760.20 1.440 *
=====
BENDS Ebend = 0.5*k(a-ao)^2
-----
Atoms          pot
i - j - k    type K      theta   NOTES
=====
*   C_2   *     1       78.79 120.00 WHITE_77
*   C_3   *     1       65.66 109.50 WHITE_77
*   C_ar  *     1       78.79 120.00 *
C_ar C_2 N_2 1    131.31 120.00 *
C_3 C_3 C_ar 1    78.79 109.50 *
=====
TORSIONS
-----
Atoms          pot
i - j - k - l  type k      per      NOTES
=====
*   C_2   C_2   *     2       12.5000 -2.0
*   C_1   C_3   *     2       0.0000  1.0
C_2 C_2 C_3   *     2       0.1260 -3.0
C_3 C_2 C_3   *     2       0.1260  3.0
H   C_2   C_3   *     2       0.2740  3.0
*   C_ar  C_ar  C_ar 2       2.3500 -2.0
*   C_2   C_3   C_2   2       0.1260  3.0
*   C_2   C_3   C_3   2       0.1260  3.0
C_3 C_3 C_3   C_3  0       0.5000  3.0       no torsion potential
C_2 C_2 C_3   C_2  2       0.1260 -3.0
C_3 C_3 N_2   C_2  1       0.5000  4     180.0 This and the next 3 lines
&                   0.1500  3     180.0 are part of a multi-component
&                   0.5300  1     0.0 Fourier potential
C_3 C_3 C_2   N_2  1       0.1000  4     0.0
&                   0.0700  2     0.0 '&' is a continuation marker
=====
OUT-OF-PLANE
-----
Atoms          pot
i - j - k - l  type K      NOTES
=====
*   *   C_2   *     2       480  TRIPPOS_85
*   *   N_2   *     2       120  TRIPPOS_85
H   H   N_2   C_3  2       120  TRIPPOS_85
C_3 H   N_2   *     2       120  TRIPPOS_85

```

(continues on next page)

(continued from previous page)

```
=====
VAN DER WAALS
atom(s)      Emin     Rmin      gamma NOTES
=====
C_3          0.1070   3.4000   12.00
C_2          0.1070   3.4000   12.00
C_ca         0.1070   3.4000   12.00
C_ar         0.1070   3.4000   12.00
C_1          0.1070   3.4000   12.00
N_3          0.0950   3.1000   12.00
N_2          0.0950   3.1000   12.00
N_2 - N_2  2 0.0950   3.1000   12.00 purely repulsive potential for this pair
=====

type    charge(e)  NOTES
=====
OW     -0.82       TIP3P water model
HW     0.41        TIP3P water model
=====
```

### Section by Section Description

**FORCE\_FIELD\_SETTINGS** Key block (required) This key block specifies various global options for the force field file, mostly concerned with the treatment of the non-bonded potentials.

```
FORCE_FIELD_SETTINGS
=====
ELSTAT_1-4_SCALE      0.5
VDW_1-4_SCALE         0.5
VDW_DEFAULT_POTENTIAL 1      (1:6-12)
DIELECTRIC_CONSTANT    1.000
=====
```

**ELSTAT\_1-4\_SCALE & VDW\_1-4\_SCALE** Most force fields scale the non-bonded interactions by a factor of 0.5 if the atoms are the terminal atoms of a defined torsion. This scaling factor, which is termed the 1-4 scaling factor, can also be different for the electrostatic potential and for the Van der Waals potentials and thus they are separately defined in the input.

**VDW\_DEFAULT\_POTENTIAL** Only the Lennard Jones potential (option 1) is implemented. The Lennard Jones interaction energy between atoms A and B is defined as a function of the distance between atoms A and B ( $R^{AB}$ ). The two parameters are  $D_0$  and  $R_0$ .

$$E_{VDW}(R^{AB}) = D_0 \left[ \left( \frac{R_0}{R^{AB}} \right)^{12} - 2 \left( \frac{R_0}{R^{AB}} \right)^6 \right]$$

**DIELECTRIC\_CONSTANT** This option is ignored.

**BONDS** Key block (required) This key block specifies the potential type and parameters for each kind of MM bond stretching interaction. An example is given below.

```
BONDS
Atoms pot      K           ro      NOTES
i - j type    (kcal/molA^2) (Ang)
=====
CA CA 1      938.0        1.400  amber95
CT CT 1      620.0        1.526  amber95
=====
```

(continues on next page)

(continued from previous page)

HC Zr	0	0.0	no potential found
=====			

The first two columns are the atom types (up to four characters long) and the third column is an integer specifying the potential type.

BOND potential type		constants required (in order)
0	no potential	none
1	simple harmonic: $E_b^{ij} = 1/2 K (R_{ij} - R_0)^2$ AMBER95, Sybyl	K, R <sub>0</sub>

**BENDS** Key block (required) This key block specifies the potential type and parameters for each kind of MM bond angle interaction. An example is given below.

BENDS				
Atoms	pot	k	ao	NOTES
i - j - k	type	(kcal/mol)	deg	
=====				
* CA *	1	70.00	120.00	example of wild card
* CA CA	1	126.00	120.00	
CA CA N2	1	140.00	120.10	amber95 N2-CA-CM
CA CA CT	1	140.00	120.00	amber95
=====				

The first three columns specify the atom types and the fourth column is an integer specifying the potential type. The angle bend potential types are described in the table below with the additional constants required.

BEND potential type		constants required (in order)
0	no potential	none
1	theta harmonic: $E_\theta^{ijk} = 1/2 K_\theta (\theta_{ijk} - \theta_0)^2$ AMBER95, SYBYL	$K_\theta$ , $\theta_0$ ( $\theta$ in degrees)

Notice that wild cards can be specified for both terminal positions of the bend or just one as in the example above. It is important that the parameters be ordered from the least specific (those containing the most wild cards) to the most specific parameters.

**TORSTIONS** Key block (required) This key block specifies the potential type and parameters for each kind of MM bond torsion interaction. For the bond stretching and bending potentials, only one potential has to date been implemented since both AMBER and SYBYL both use simple harmonic potentials. However, AMBER and SYBYL use different functional forms to represent the torsion potentials, each with their own set of parameters. The AMBER and SYBYL torsional potentials used in this program are defined in the table below.

TORSION potential type		constants required (in order)
0	no potential	none
1	$E_{tors} = \frac{K_{tor}}{N_{tors}} [1 + \cos(n\phi - \phi_o)]$ AMBER:	$K_i, n_i$ (periodicity-integer), $\phi_{0,i}$ (phase shift)
2	SYBYL: $E_{tors} = \frac{1}{2} K_{tor} [1 + \cos(n\phi_o) \cos(n\phi)]$	$K, s$

Notice that the two potentials have a different number of parameters. For example, when the program reads ‘potential type’ number 1, it will expect three parameters  $K_i$ ,  $n_i$ ,  $\phi_{0,i}$ . Further notice that the AMBER torsional potential is a sum of Fourier components (this is what the index i refers to).

Below is an example of the TORSIONS key block, made up of AMBER force field types.

TORSIONS											
Atoms			pot	per.	shift						
i	-	j	-	k	-	l	type	k	n	to	NOTES
<hr/>											
*	CV	NB	*	1	2.4000	2	180.0		JCC, 7, (1986), 230		
*	CW	NA	*	1	1.5000	2	180.0		JCC, 7, (1986), 230		
&				0.1000		3		0.0			
C	N	CT	C	1	0.2000	2	180.0				
N	CT	C	N	1	0.4000	4	180.0				
&				1.3500		2		180.0			
&				0.7500		1		180.0			
CT	CT	N	C	1	0.5000	4	180.0				
<hr/>											

Most AMBER torsion potentials are not specific to all four atoms i-j-k-l, but only on the central two, j-k. Wild cards are specified with the ‘\*’ symbol as illustrated above. Again, the ordering is important. The parameters should be ordered from least specific (those containing the most wild cards) to most specific. The AMBER torsion potential can be composed of more than one Fourier component for a single torsion potential. Additional Fourier components are specified with the ‘&’ continuation symbol as in the example above. At the moment, up to 6 Fourier components are allowed. Notice that the individual components need not be specified in any particular order. In the above example key block, there are only 5 torsional potentials defined, not 8. Two of the potentials are composed of more than one Fourier component as indicated by the ‘&’ continuation line. Below is an example of the TORSIONS key block for the SYBYL force field. Notice that the potential types are all ‘2’. There are fewer parameters and no multi component potentials. Also, some potentials are defined with two or only one wild card.

TORSIONS						
Atoms			pot			
i	-	j	-	k	per	NOTES
<hr/>						
*	C_ar	S_3	*	2	1.0000	3.0
*	S_3	S_3	*	2	0.0000	2.0
C_2	C_2	C_3	*	2	0.1260	-3.0
C_3	C_2	C_3	*	2	0.1260	3.0
						WHITE_77

(continues on next page)

(continued from previous page)

H	C_2	C_3	*	2	0.2740	3.0	*
*	C_ar	C_ar	C_ar	2	2.3500	-2.0	*
*	C_2	C_3	C_2	2	0.1260	3.0	WHITE_77
*	C_2	C_3	C_3	2	0.1260	3.0	WHITE_77
*	C_2	C_3	H	2	0.2740	3.0	WHITE_77
*	C_3	C_3	H	2	0.3200	3.0	MC_88
O_2	C_2	C_3	C_3	2	0.7000	-3.0	JL_ES_
O_co	C_2	C_3	C_3	2	0.7000	-3.0	MAC_1
C_2	C_3	C_3	C_2	2	0.0400	3.0	WHITE_77
C_2	C_3	C_3	C_3	2	0.1260	3.0	WHITE_77
<hr/>							

One can also mix different potential types within the same force field file, as illustrated below. In this example, there are three potentials. The first two are SYBYL type potentials whereas the last one is a multi component AMBER potential.

H	C_2	C_3	*	2	0.2740	3.0	
*	C_ar	C_ar	C_ar	2	2.3500	-2.0	
N	CT	C	N	1	0.4000	4	180.0
&					1.3500	2	180.0
&					0.7500	1	180.0

**OUT-OF\_PLANE** Key block (required) This key block specifies the potential type and parameters for each kind of MM out of plane bend. This potential is sometimes referred to as the inversion potential or improper torsions (depending on the force field). The potential types currently supported are provided in the table below.

out-of-plane potential type	description	constants required (in order)
0	no potential	none
1	AMBER: $E_{inv} = K [1 + \cos(n\phi - \phi_0)]$	K, n, $\phi_0$ ( $n=2, \phi_0 = 180^\circ$ for planar, $n=3, \phi_0 = 120^\circ$ for tetrahedral)
2	SYBYL: $E_{oopl} = K d^2$ d is the distance of the plane in Å	K

An example of the key block for the AMBER type potentials is given below. It is important to realize that the atom k is the **atom k is the central atom**. (We have adopted the somewhat odd standard of AMBER in this respect).

OUT-OF-PLANE							
<hr/>							
Atoms			pot				
i - j - k - l			type	K	to		NOTES
*	*	CA	H4	1	1.10	180.0	bsd.on C6H6 nmodes
*	*	CA	H5	1	1.10	180.0	bsd.on C6H6 nmodes
*	O2	C	O2	1	10.50	180.0	JCC, 7, (1986), 230
*	N2	CA	N2	1	10.50	180.0	JCC, 7, (1986), 230
*	CT	N	CT	1	1.00	180.0	JCC, 7, (1986), 230
CK	CB	N*	CT	1	1.00	180.0	
<hr/>							

**VAN DER WAALS** Key block (required) This key block specifies the potential type and parameters for each kind of MM van der Waals interaction between two atoms. A sample key block is shown below:

atom(s)	type	emin	rmin	alpha	NOTES
CA		-0.0860	3.81600	12.00	amber95
HA		-0.0150	2.91800	12.00	amber95
Ni - HA	2	-0.0480	2.7	12.00	NOTE potential type
Ni - CA	D	-0.0480	2.7	12.00	default potential

The van der Waals key block is somewhat different than the previous key blocks, because generally not every atom pair is defined with its own parameters. Rather, the parameters are assigned on a per atom basis and then special combination rules are used to construct the parameters for each atom pair combination. For this reason, the type is defined separately in the FORCE\_FIELD\_SETTINGS key block, although currently only the Lennard-Jones 6-12 potential is implemented, although currently only the Lennard-Jones 6-12 potential is implemented

For each type of van der Waals interaction, the program first scans the key block for pair specific parameters. The three sample lines below specify pair-specific potentials. The two atom types must be separated by a hyphen with spaces between the hyphen and the atom type. Following the specification of the atom pair, the potential type is defined. If D or d is specified here, then this means to use the default potential type. Following the potential type are the parameters needed for that potential type (see above table).

CA - CA	1	0.0860	3.81600	12.00	amber95
NI - HA	0				
NI - CA	D	0.0480	2.7	12.00	default potential type

If a pair specific parameter can't be found, then the program looks for individual atom parameters corresponding to each of the atom types in the pair. The pair specific parameters are then constructed from combination of the two individual atom parameters using the following combination rules:

VDW potential type		
1	Lennard-Jones 12-6	$D_{ij} = (D_i * D_j)^{1/2}$ , $R_{ij} = (R_i + R_j)/2$
2	Exponential-6 or Buckingham	$D_{ij} = (D_i * D_j)^{1/2}$ , $R_{ij} = (R_i + R_j)/2$ $\zeta_{ij} = (\zeta_i * \zeta_j)^{1/2}$
3	Purely Repulsive	$D_{ij} = (D_i * D_j)^{1/2}$ , $R_{ij} = (R_i + R_j)/2$ $\zeta_{ij} = (\zeta_i * \zeta_j)^{1/2}$

When individual atom parameters are not used, no potential type is specified since the default potential type is always used. An example is given below.

CA	0.0860	3.81600	12.00	amber95
HA	0.0150	2.91800	12.00	amber95

The ability to define pair specific parameters is especially useful for those force fields that have different combination rules than used in the program. For example, Jorgensen's TIP3P water force field uses geometric averages for both  $D_{ij}$  and  $R_{ij}$ .

**MASSES & ATOM LABELS** Key block (required) This key block specifies the default masses for each MM atom type and the element label for each MM atom type. The masses are not used by the engine.

A sample key block is shown below:

MASSES & ATOM LABELS		
=====		
Ni	Ni	58.70
CM	C	12.011
CA	C	12.011
CT	C	12.011
HC	H	1.0079
HA	H	1.0079
=====		

The first column is the MM atom type, the second is the corresponding atom element and the third column is the mass of the atom type. The atoms do not have to be specified in any particular order.

**CHARGES** Key block (optional) This key block specifies the parameters for the charges on the atoms by atom type.  
NOTE: Charges can also be specified on a per atom basis in the System block of the AMS input file.

CHARGES		
=====		
atoms	initial	
label	charge	
=====		
OW	-0.8	
HW	0.4	
=====		



---

CHAPTER  
**EIGHT**

---

## POTENTIAL SHAPES

Setting the *Verbosity* (page 10) to Verbose the engine prints the potential formula and the parameters used.

The ForceField engine has a couple of potentials defined.

- Stretch: harmonic

$$V^{\text{stretch/harm}} = \frac{1}{2} f_c (r - r_0)^2$$

- Angle: harmonic and cyclic

$$V^{\text{bend/harm}} = \frac{1}{2} f_c (\phi - \phi_0)^2$$
$$V^{\text{bend/cycl}} = f_c \sum_{m=0}^n c_m \cos(m\phi)$$

- Torsions: cyclic, possibly linearly combined. The same torsion occurs more than once in the printed table, and the energies are added.

$$V^{\text{torsion/harm}} = \frac{1}{2} f_c (\phi - \phi_0)^2$$
$$V^{\text{torsion/cycl}} = f_c \sum_{m=0}^n c_m \cos(m\phi)$$

- Inversions: either angle or distance based. The angle based one depends on the order of the three atoms connected to the central atom. UFF averages over the three permutations.

$$V^{\text{inversion/harm}} = \frac{1}{2} f_c (\phi - \phi_0)^2$$
$$V^{\text{inversion/cycl}} = f_c \sum_{m=0}^n c_m \cos(m\phi)$$
$$V^{\text{inversion/amber}} = f_c (1 + \cos(2\phi - \phi_0))$$
$$V^{\text{inversion/dist}} = f_c d^2$$

- Dispersion: Lennard-Jones. Neglect up to second neighbors, possibly scale contribution from third neighbors.

$$V^{\text{dispersion/LJ}} = d ((x/r)^{12} - 2 * (x/r)^6)$$

- Coulomb: Neglect up to second neighbors, possibly scale contributions from third neighbors.

In general which formula is used depends on the parameter files. Note that the scaling of the third neighbors contributions is only possible when using .ff parameter files.



---

**CHAPTER  
NINE**

---

## **PERIODIC FORCEFIELD**

The forcefield engine can be used to optimize the geometries of periodic systems. When specifying bonds, via the System%Bondorders key block, one should also specify the bonds that pass through a cell boundary. The GUI does this automatically. You can also simply set the key System%GuessBonds to true, and then UFF-guessed bonds will be used.

When you are having charges, Ewald summation will be used to calculate the Coulomb interaction. Currently this will be fairly slow for 1D and 2D periodic systems, as the classical Ewald trick cannot be applied.



---

**CHAPTER  
TEN**

---

**REFERENCES**

1. A.K. Rappe, C.J. Casewit, K.S. Colwell, W.A. Goddard III, and W. M. Skiff, *UFF, a Full Periodic Table Force Field for Molecular Dynamics Simulations*, *Journal of the American Chemical Society* 114, 10024-10035 (1992). (<https://doi.org/10.1021/ja00051a040>)
2. A.K. Rappe, W.A. Goddard III, *Charge Equilibration for Molecular Dynamics Simulations*, *The Journal of Physical Chemistry* 95, 3358-3363 (1991). (<https://doi.org/10.1021/j100161a070>)
3. M. O'Keeffe and N.E. Brese, *Atom sizes and bond lengths in Molecules and Crystals*, *Journal of the American Chemical Society* 113, 3226-3229 (1991). (<https://doi.org/10.1021/ja00009a002>)
4. S.L. Mayo, B.D. Olafson, W.A. Goddard III, *DREIDING: A Generic Force Field for Molecular Simulations*, *The Journal of Physical Chemistry* 94, 8897-8909 (1990). (<https://doi.org/10.1021/j100389a010>)
5. C.J. Casewit, K.S. Colwell, A.K. Rappe, *Applications of a Universal Force Field to Main Group Compounds*, *Journal of the American Chemical Society* 114, 10046-10053 (1992). (<https://doi.org/10.1021/ja00051a042>)
6. C.J. Casewit, K.S. Colwell, A.K. Rappe, *Application of a Universal Force Field to Organic Molecules*, *Journal of the American Chemical Society* 114, 10035-10046 (1992). (<https://doi.org/10.1021/ja00051a041>)

For calculations with the UFF4MOF parameters:

7. M.A. Addicoat, N. Vankova, I.F. Akter, and T. Heine, *An extension of the Universal Force Field to Metal-Organic Frameworks*, *J. Chem. Theory Comput.* 10, 880-891 (2013) (<https://doi.org/10.1021/ct400952t>)

For calculations with the UFF4MOFII parameters:

8. D.E. Coupry, M.A. Addicoat, and T. Heine, *An Extension of the Universal Force Field for Metal-Organic Frameworks*, *J. Chem. Theory Comput.* 12, 5215-5225 (2016) (<https://doi.org/10.1021/acs.jctc.6b00664>)

For calculations with the APPLE&P forcefield:

9. O. Borodin, *Polarizable Force Field Development and Molecular Dynamics Simulations of Ionic Liquids*, *J. Phys. Chem. B* 113, 11463–11478 (2009) (<https://doi.org/10.1021/jp905220k>)



## KEYWORDS

### 11.1 Links to manual entries

**forcefield:**

- [APPLE&P](#) (page 16)
- [AllowMissingParameters](#) (page 14)
- [AntechamberIntegration](#) (page 7)
- [AntechamberTask](#) (page 7)
- [BondsUsage](#) (page 10)
- [CheckDuplicateRules](#) (page 14)
- [DipoleConvergenceThreshold](#) (page 16)
- [EnergyTerms](#) (page 12)
- [EwaldSummation](#) (page 11)
- [ForceFieldFile](#) (page 15)
- [GuessCharges](#) (page 13)
- [GuessChargesConfig](#) (page 13)
- [LoadCharges](#) (page 14)
- [NeighborListSkin](#) (page 10)
- [NonBondedCutoff](#) (page 9)
- [Type](#) (page 9)
- [UFF](#) (page 15)
- [Verbosity](#) (page 10)

### 11.2 Summary of all keywords

#### **AllowMissingParameters**

**Type** Bool

**Default value** No

**Description** When parameters are not found for bonds, angles, dihedrals, or inversions, the first entry in the database will be used.

#### **AntechamberIntegration**

**Type** Bool

**Default value** No

**GUI name** Automatic atom typing

**Description** EXPERIMENTAL: Use the Antechamber program to automatically determine atom types for the GAFF force field. This may run a geometry optimization with MOPAC under the hood in order to determine the charges (see keyword AntechamberTask), which might not work for very large systems.

### **AntechamberTask**

**Type** Multiple Choice

**Default value** GeometryOptimization

**Options** [GeometryOptimization, SinglePoint]

**Description** If antechamber is invoked to guess atomtypes and charges (GAFF force field), select the task for charge guessing with MOPAC

### **APPLE&P**

**Type** Block

**Description** Options for the APPLE&P force field.

#### **MuMu14Scaling**

**Type** Float

**Default value** 1.0

**GUI name** Mu-Mu 3rd-neighbor scaling

**Description** Scaling factor for dipole-dipole interactions between atoms connected to 3rd order (via a dihedral).

#### **QMu14Scaling**

**Type** Float

**Default value** 0.8

**GUI name** Q-Mu 3rd-neighbor scaling

**Description** Scaling factor for charge-dipole interactions between atoms connected to 3rd order (via a dihedral).

#### **QQ14Scaling**

**Type** Float

**Default value** 0.8

**GUI name** Q-Q 3rd-neighbor scaling

**Description** Scaling factor for charge-charge interactions between atoms connected to 3rd order (via a dihedral).

#### **RD14Scaling**

**Type** Float

**Default value** 1.0

**GUI name** RD 3rd-neighbor scaling

**Description** Scaling factor for repulsion/dispersion interactions between atoms connected to 3rd order (via a dihedral).

### **BondsUsage**

**Type** Multiple Choice

**Default value** Auto

**Options** [Input, None, Guess, Auto]

**Description** Controls what bonds are used by the engine. The choice auto means: guess in case there are no bonds. Guessing only happens at the first MD step, or first geometry optimization step.

#### **CheckDuplicateRules**

**Type** Bool

**Default value** Yes

**Description** The database could contain duplicate entries. For torsions this is a feature, and the potentials will be added. For all other terms this is not allowed, and if detected the program stops. One should fix the database or set the checking to false. As always the last entry will be used.

#### **DipoleConvergenceThreshold**

**Type** Float

**Default value** 1e-06

**Unit** a.u.

**Description** Convergence criterion for induced point dipoles, in atomic units. When the length of every atomic delta\_mu vector between two iterations becomes below the tolerance, the procedure is considered converged.

#### **DoChargeCheck**

**Type** Bool

**Default value** No

**Description** Check that the sum of atomic (partial) charges equals the total charge of the system.

#### **EnergyTerms**

**Type** Block

**Description** expert key, that allows you to disable specific energy terms.

#### **Angle**

**Type** Bool

**Default value** Yes

**Description** Whether to use angle (bend) energy.

#### **Coulomb**

**Type** Bool

**Default value** Yes

**Description** Whether to use coulomb energy.

#### **Dispersion**

**Type** Bool

**Default value** Yes

**Description** Whether to use dispersion energy.

### Inversion

**Type** Bool

**Default value** Yes

**Description** Whether to use inversion energy.

### Stretch

**Type** Bool

**Default value** Yes

**Description** Whether to use stretch energy.

### Torsion

**Type** Bool

**Default value** Yes

**Description** Whether to use torsion energy.

### EwaldSummation

**Type** Block

**Description** Configures the details of the particle mesh Ewald (PME) summation of the Coulomb interaction.

#### Alpha

**Type** Float

**Default value** -1.0

**Unit** 1/Angstrom

**Description** This parameter shifts the workload from real space (smaller alpha) to reciprocal space (larger alpha). Using a larger [Alpha] without decreasing [GridSpacing] may increase the error in the reciprocal-space contribution. Set to zero to disable the reciprocal-space Ewald part. Negative value means the [Alpha] will be determined automatically from the [Tolerance] and [RealSpaceCutoff] values.

#### Enabled

**Type** Bool

**Default value** Yes

**Description** Set to false to use real-space pair summation instead of the Ewald, which is the default and the only option for molecules, 1D and 2D periodic systems.

#### GridSpacing

**Type** Float

**Default value** 0.5

**Unit** Angstrom

**Description** Grid spacing in the particle mesh Ewald method. Smaller grid spacing will make the reciprocal energy calculation more accurate but slower. Using a larger [Alpha] value may require a smaller GridSpacing to be accurate.

#### RealSpaceCutoff

**Type** Float

**Default value** 0.0

**Unit** Angstrom

**Description** Set the cutoff value for the real-space summation. Zero means the internal defaults will be used depending on the [Alpha] (if Alpha=0 then the cutoff will be set to 50 Bohr, otherwise to 20 Bohr).

#### **tolerance**

**Type** Float

**Default value** 1e-10

**Description** Value of the error function that should be used to determine the cutoff radius for real-space Ewald summation if [Alpha] is set on input. Alternatively, if the [RealSpaceCutoff] is set but [Alpha] is not then the [Tolerance] value affects the [Alpha]. Larger values will make the real-space summation faster but less accurate.

#### **ForceFieldFile**

**Type** String

**Default value**

**GUI name** Force field library

**Description** Path to the force field parameter file

#### **ForceFieldPatchFile**

**Type** String

**Default value**

**GUI name** Force field patch file

**Description** Path to the force field patch parameter file (additional parameters, missing from main file). Cannot be used when atomtypes are guessed.

#### **GuessCharges**

**Type** Bool

**Default value** No

**Description** Use another engine to calculate/guess the charges to be used by the force field.

#### **GuessChargesConfig**

**Type** Block

**Description** Guess charges to be used by the forcefield

#### **EngineType**

**Type** String

**Default value** dftb

**Description** Engine that can calculate or guess charges

#### **LinearizationEnergyForRepulsion**

**Type** Float

**Default value** 3.0

**Unit** Hartree

**Description** The Lennard Jones potential becomes extremely repulsive at short distances. The distance is determined where the potential reaches this threshold, for smaller distances a linear expression is used, reducing the repulsion.

**LoadCharges**

**Type** Block

**Description** Load charges from a file to be used as forcefield charges

**File**

**Type** String

**Description** Name of the (kf) file

**Section**

**Type** String

**Default value** AMSResults

**Description** Section name of the kf file

**Variable**

**Type** String

**Default value** Charges

**Description** variable name of the kf file

**NeighborListSkin**

**Type** Float

**Default value** 2.5

**Unit** Angstrom

**Description** Thickness of the buffer region added to the NonBondedCutoff when building a neighbor list.

**NonBondedCutoff**

**Type** Float

**Default value** 15.0

**Unit** Angstrom

**Description** Distance beyond which the non-bonded pair interactions (Coulomb and Van der Waals) will be ignored.

The interactions are smoothly damped starting from 0.9\*NonBondedCutoff.

Has no effect on the Coulomb term for periodic systems, as Ewald summation is used.

**Type**

**Type** Multiple Choice

**Default value** UFF

**Options** [UFF, Amber95, GAFF, Tripos5.2, APPLE&P, UserDefined]

**Description** Type of force field to be used

**UFF**

**Type** Block

**Description** Option for the UFF force filed.

**AtomTypesFile**

**Type** String

**Default value** mmatomtypes\_db

**Description** Expert option: Select the file that defines how UFF determines the atom types

**Database**

**Type** String

**Default value** general\_db

**Description** Expert option: Select the file that defines the UFF parameters per atom type

**ElementsFile**

**Type** String

**Default value** elements\_db

**Description** Expert option: Select the file that defines the elements known to UFF

**Library**

**Type** Multiple Choice

**Default value** UFF

**Options** [UFF, UFF4MOF, UFF4MOF-II]

**GUI name** Force field library

**Description** Selects the used parameter library.

**Verbosity**

**Type** Multiple Choice

**Default value** Silent

**Options** [Silent, Normal, Verbose, VeryVerbose]

**Description** Controls the verbosity of the engine.



## **INDEX**

### **A**

antechamber, [7](#)